



AUTO-TUNE PRO 11

USER GUIDE

Introducing Auto-Tune Pro 11	12
What is Auto-Tune Pro 11?	12
Quick Start – License Activation	13
Activation Instructions	13
Step 1: Install Auto-Tune Central	13
Step 2: Open Auto-Tune Central and Log In	13
Step 3: Navigate to the Redeem a License Tab	14
Step 4: You're all set!	14
Step 5: Open Auto-Tune Pro 11 In Your DAW	14
Pro Tools	15
Logic Pro	15
Ableton Live	15
Cubase	15
Studio One	15
FL Studio	15
What's new in Auto-Tune Pro 11?	16
Harmony Player	16
Auto Mode New Features	16
Graph Mode New Features	16
Global Improvements	17
What Type of Audio is Appropriate for Auto-Tune?	18
Auto Mode Overview	19
Basic and Advanced Views	20
Graph Mode Overview	21
Graph Mode Workflow	22
Correction Objects	23
Notes	23
Curves	24
Lines	24
Pitch Contours	25
Red	25
Blue	25
Green	25
Time Correction	26
Non-Destructive Editing	26
Time Shifting Limits	27
Managing Time Correction Data Files	27

Global Controls	28
Auto-Tune Central	28
Multi-View List	28
Undo	29
Redo	29
Settings	29
Bypass	29
Tracking	30
Input Type	30
Input Type – Learn	31
Key	31
Scale	31
Auto-Key	32
Preset Manager	34
Preset Dropdown Menu	34
Preset Favorite Button	35
Random Preset Button	35
Preset Management Menu	35
Auto/Graph Mode Switch	36
Modern/Classic Mode Toggle	36
Harmony Player Toggle	37
Formant Correction	37
Transpose	38
Conform To Scale	38
Detune	39
Mix Knob	39
Basic Auto Mode Controls	40
Advanced	41
Retune Speed	41
Flex-Tune	41
Humanize	42
Natural Vibrato	42
Pitch Display and Pitch Change Meter	43
Pitch Display	43
Pitch Change Meter	43
Hold	43
The Keyboard	44

On	44
Bypass	44
Remove	45
Keyboard Edit	45
Latch	45
Advanced Auto Mode Controls	47
Vibrato Controls	48
Shape	48
Off	48
Sine Wave	48
Sawtooth	48
Square	48
Rate	49
Delay	49
Onset Rate	49
Variation	49
Pitch Amount	50
Amplitude Amount	50
Formant Amount	50
Scale Controls	51
Bypass	51
Remove	52
Cents Display	52
Set Major/Set Minor	52
Set All	52
Bypass All	53
Remove All	53
Ignore Vibrato	53
MIDI Functions	54
To Notes	55
Learn Scale	55
All Octaves	55
MIDI Mapping	56
MIDI Learn	57
MIDI CC	57
Clear	57
Harmony Player Controls	58

Mixer	59
Input	59
Harmony Interval	59
Pan	60
Naturalize	60
Transition Time	60
Pitch Variation	61
Timing Variation	61
Harmony Voice Modules	62
Solo	62
Interval	62
Trigger Latch	63
Formant	63
Pan	63
Width	63
Level	64
Trigger	64
Trigger All Button	64
Latch	64
Envelope Controls	65
Attack	65
Release	65
Equalizer Controls	66
High Pass, Band Pass, Low Pass Filter Selector	66
Frequency	66
Slope	67
Q	67
Level	67
Gate & Width Controls	68
Threshold	68
Side Chain	68
Int	68
Ext	69
Width	69
Graph Mode Controls	70
Main Graph and Waveform Graph	71
Main Graph	71

Toolbar Show/Hide Buttons	71
Waveform Graph	72
All/Tie Switch	72
Zoom States	73
Pitch Tracking and Correction Objects	74
Track Pitch or Pitch & Time	74
Create Curves	75
Create Curves From Audio	75
Create Curves From Auto Mode	75
Create Notes	76
Create Notes From Audio	76
Create Notes From MIDI	76
Density	77
Per Object Controls	79
Retune Speed	79
Vibrato	80
Formant	80
Selection Tools	81
Select All	81
Clear	81
Pitch Correction Objects	81
Time Changes	81
Both Pitch and Time	81
Copy	82
Cut	82
Paste	82
Drawing Tools	83
Line Tool	83
Curve Tool	84
Note Tool	84
Editing Tools	85
Arrow Tool	86
Range Tool	88
Split Tool	88
Zoom Tool	88
Hand Tool	89
Nudge	90

Time Correction Tools	91
Point Tool	91
Region Tool	92
Info Bar	94
Clock	94
Cursor	94
Legend	94
Detected	95
Object	95
Output	95
ARA2: Audio Random Access	96
Background	96
What is ARA2?	96
Compatible DAW's	96
ARA2 Features	97
Time Ruler	97
Bi-Directional Synchronization	97
Looping Points	98
ARA2 Workflow Differences	99
Automatic Data Transfer	99
Re-Track Button	99
Logic Pro: ARA2 Workflow Notes	100
How to Instantiate	100
Dependent vs. Independent Copies	101
Duplicating/Copying Regions:	101
Duplicating/Copying Tracks with Auto-Tune Pro (ARA):	101
Studio One: ARA2 Workflow Notes	103
How to Instantiate	103
Dependent vs. Independent Copies	103
Duplicating/Copying Events:	103
Duplicating/Copying Tracks with Auto-Tune Pro (ARA):	103
Cubase: ARA2 Workflow Notes	105
How to Instantiate	105
Dependent vs. Independent Copies	106
Duplicating/Copying Events:	106
Duplicating/Copying Tracks with Auto-Tune Pro (ARA):	106
Quick Settings and Preferences	108

Quick Settings	109
Preferences...	109
View Tooltips	109
View Help Topics	109
Reset Window Size	109
Reset Warning Dialogs	110
Use Low Latency	110
Move Data Folder	110
Rename Data Folder	111
Show in Graph Mode	111
Waveform in Main Graph	111
Waveform Graph	111
Tracked MIDI	112
Pitch Lanes	112
Graph Mode Settings	113
Auto Scroll	113
Snap to Note	113
Play Tone When Moving Notes	114
Time Display	114
Enable Time Correction Edits	114
Version Number	114
Preferences Window: Introduction	115
General Preferences	116
Non-ARA Opens Showing	116
Appearance	117
Auto-Key Detection	117
Knob Control	117
Detune Display	118
Pitch Reference	118
Scales	118
Use OpenGL Graphics	119
MIDI Input Channel	119
Graph Mode Preferences	120
After Tracking	120
Zoom After Tracking	121
Play Tone When Moving Note Objects	121
Time Ruler Displays	121

Show Waveform in Main Graph	121
Show Waveform in Note Objects	122
Show Waveform Graph	122
Waveform Graph Shows	122
Show Input Pitch Curves	123
Show Output Pitch Curves	123
Display Vertical Line at Cursor Position	123
Scroll Graph	123
Vertical Scrolling	124
Use Custom Cursors For Editing Tools	124
Disable Cursors While Playing	125
Show Note Labels On	125
Default Retune Speed For	125
Key Binding Preferences	126
Tutorials	127
The Auto-Tune Effect	128
What is it?	128
How To Recreate It	128
Auto Mode	128
Graph Mode	129
Auto Mode Basics	131
To Begin	131
Scale and Key Settings	131
Remove Notes	132
Bypass Notes	132
Retune Speed	132
Detune	133
Create Vibrato	134
Flex-Tune	135
To begin	135
No Flex-Tune	135
Some Flex-Tune	135
More Flex-Tune	136
Ignore Vibrato	137
Auto Mode	137
Graph Mode (with Create Curves from Auto Mode)	138
Natural Vibrato Function	139

Transpose and Formant Control	140
Graph Mode Basics	141
Track Pitch	141
Zoom Tool	142
Line Tool	142
Curve Tool	143
Multi Tool	143
Split Tool	144
Create Curves and the Line Tool	145
Create Curves	145
Line Tool	147
Create Curves from Auto Mode	148
Create Notes	151
Time Correction	154
The Region Tool	154
The Point Tool: Adjusting an Ending	156
The Point Tool: Adjusting an Internal Syllable	158
Creative Time Editing	160
Keyboard Shortcuts	163
General	163
Auto Mode Keyboard	163
Graph Mode	164
MIDI Mapping Master List	165
Global Controls	165
Pitch Correction Controls	165
Advanced Mode Controls	165
Vibrato Controls	165
Scale Controls	166
MIDI Functions	166
Harmony Player Controls	166
Harmony Voice Module Controls	166
Envelope Controls	168
Equalizer Controls	168
Gate/Stereo Width Controls	168

Introducing Auto-Tune Pro 11



What is Auto-Tune Pro 11?

For over twenty five years, Auto-Tune has been the world standard for professional pitch and time correction, as well as the tool of choice for the signature [vocal effect](#) of modern popular music.

Auto-Tune Pro 11 is the latest and most complete version of Auto-Tune, featuring two modes of operation: Auto Mode, optimized for low latency real-time pitch correction and effects, and Graph Mode, enabling unparalleled versatility, and detailed graphical editing of pitch and timing.

Auto-Tune Pro 11 is packed with new features and a brand new, streamlined interface, redesigned to maximize efficient workflow and usability for beginners and experts alike.

Quick Start – License Activation

Activation Instructions

Before we can use Auto-Tune Pro 11, we need to activate our license first using the Auto-Tune Central application. Please follow the steps below, or watch our [instructional video](#) to get started:

Step 1: Install Auto-Tune Central

Visit our website [here](#) to download the latest installer for Auto-Tune Central. After downloading, run the installer.

After installation is complete, you can find Auto-Tune Central in your computer's applications folder:

MacOS

/Applications

Windows

C:\Program Files\Antares Audio Technologies

Step 2: Open Auto-Tune Central and Log In

Enter your Antares account email address and password to log in.

If you don't have an account yet, you can create one within Auto-Tune Central.

If you purchased your plug-in or subscription through antarestech.com, navigate to the "Plug-Ins" tab to install and activate your license. Once your license has been activated, you're ready to open the plug-in in your DAW!

If you purchased through a third party, please follow the steps below.

Step 3: Navigate to the Redeem a License Tab

In the top banner of Auto-Tune Central, select "Redeem a License." Enter your 25-digit registration code, then select "Redeem and Activate."

Step 4: You're all set!

Now you can use your Antares plug-in(s) in your DAW! Navigate to the "Plug-Ins" tab to install and manage your license activations.

For the latest DAW Compatibility information, please visit [this page](#) on our website.

Step 5: Open Auto-Tune Pro 11 In Your DAW

Below, you'll find instructions on how to insert Auto-Tune Pro 11 onto a track in various compatible DAWs:

Pro Tools

Choose an empty insert slot on one of your audio tracks, instrument tracks, or buses. Then select Auto-Tune Pro 11 from the pop-up menu in either the Dynamics or EQ category.

Logic Pro

Choose an empty insert slot on one of your audio tracks, instrument tracks or buses and select Auto-Tune Pro 11 from the pop-up menu. You will find Auto-Tune Pro 11 in: *Audio Units > Antares* section (named Auto-Tune Pro).

Ableton Live

In either Session or Arrangement View, select the track you would like to place Auto-Tune Pro 11 on by clicking the track name.

At the top left of Ableton's interface, click on the Plug-in Device Browser icon. From the plug-ins list, double-click Auto-Tune Pro 11, or drag it onto the track.

Cubase

Choose an empty insert slot, for example in the Mixer, and select Auto-Tune Pro 11 from the menu that appears.

Studio One

Click the '+' button next to the Inserts tab of an audio track, and select 'Auto-Tune Pro 11' from the drop-down menu.

GarageBand

Select the track you want to apply the plug-in to, then open the Smart Controls panel by clicking the icon or by pressing 'B' on your keyboard. Select the 'Auto-Tune Pro 11' Audio Unit from the Plug-ins dropdown menu.

FL Studio

Open the *Plugin Database* section of the *Browser*, then drag and drop 'Auto-Tune Pro 11' into the channel rack. Alternatively, you can insert "Effects" plug-ins from the Mixer by selecting the track you want to work with, and clicking one of the slots located on the right side.

For more information, please visit the FL Studio Reference Manual [here](#).

What's new in Auto-Tune Pro 11?

Harmony Player

- The [Harmony Player](#) is a brand new section of creative controls added to Auto-Tune Pro, starting in version 11. With the Harmony Player, you can create and trigger up to 4 individual harmonies (called Harmony Voices) based on your input vocal. You can adjust their controls individually, then blend their outputs together.
- Harmony Player controls can be mapped to MIDI hardware.

Auto Mode New Features

- [Conform to Scale](#) control for smart transpositions
- Improved [MIDI mapping](#) workflow

Graph Mode New Features

- Graph mode startup helper
 - The first time you open Graph Mode, you will be prompted to record audio into the graph via an instructional pop-up.
- [Toolbar Show/Hide Buttons](#) to increase on-screen working area
 - Show/Hide the Global Controls Bar
 - Show/Hide the Graph Mode Toolbar
- New [Keyboard Shortcuts](#)
 - Clutch scrolling
 - Hot keys for quickly adjusting [Per Object Controls](#) on Correction Objects
 - See the [Keyboard Shortcuts Index](#) for a list of all Keyboard Shortcuts
- [Zoom Outline](#) feature on the Waveform Graph
 - Provides a clear view of the zoom range you have selected, and which part of the waveform you're looking at in the Main Graph
- [Zoom After Tracking](#) setting to customize zoom behavior in the Main Graph after tracking audio into Graph Mode.

Global Improvements

- Larger Interface
 - Improves workflow by increasing screen real estate, reducing onscreen clutter, and allowing for more detailed control labels.
- Revamped [Preset Manager](#)
- New factory presets

What Type of Audio is Appropriate for Auto-Tune?

Auto-Tune is intended for use with a well-isolated, monophonic sound source such as a single voice, or a single instrument playing one pitch at a time. Multiple voices or instruments recorded onto the same track, or single instruments that are playing multiple pitches at the same time, cannot be accurately pitch corrected using Auto-Tune.

Noise content, or breathiness in vocal performance can sometimes also lead to tracking errors. However, this can often be remedied by adjusting the [Tracking](#) knob.

Auto Mode Overview



Unlike Graph Mode, which is designed for more precise note-by-note pitch editing, Auto Mode is optimized for real time, low latency performance, on stage or in the studio.

You can control the parameters in real time using a MIDI controller, automate them using your DAW's automation features, or simply dial in your settings and let Auto-Tune take care of the rest.

Auto-Tune Pro 11 works by continuously adjusting the pitch of the incoming audio toward a target pitch. In Auto Mode, the target pitch is determined by the current Key and Scale settings. At any given moment, the target pitch will be the active scale tone that is closest to the detected input pitch.

The set of active scale tones is specified using the [Key](#) and [Scale](#) menus, and edited with the [Keyboard](#) and the [Scale Controls](#).

The [Retune Speed](#) parameter controls how fast the input pitch is tuned toward the target pitch, with faster speeds resulting in a more pronounced effect, and more moderate speeds resulting in more subtle pitch correction.

The [Flex-Tune](#) and [Humanize](#) controls allow you to further customize the tuning and pitch variations of your track for even more transparent and natural sound correction.

The [Natural Vibrato](#) knob and [Vibrato Controls](#) in Advanced View allow you to subtly or dramatically alter the vibrato of your track.

The MIDI [To Notes](#) and [Learn Scale](#) functions allow you to define target pitches dynamically in real time using your MIDI controller.

You can also control many Auto Mode parameters using your MIDI controller. To assign a control to a particular MIDI CC message, right click on the control.

Basic and Advanced Views




Auto Mode features two different screen views: [Basic View](#) and [Advanced View](#).

Basic view hides some of the more advanced features and shows only the more commonly used controls for quick and easy access.

Advanced View shows all of the available controls, including the [MIDI Functions](#), [Vibrato Controls](#), and the [Scale Controls](#). All of the Advanced View features remain active, even when hidden in Basic View.

Graph Mode Overview



Graph Mode allows you to make detailed edits to the pitch and timing of your audio using a pitch graph and a variety of editing tools.

Auto-Tune Pro 11 works by continuously adjusting the pitch of the incoming audio toward a target pitch. In Graph Mode, the target pitch is determined by [Correction Objects](#) (Lines, Curves, and Notes) (1) that are drawn on the [Main Graph](#) (2).

Correction Objects can be automatically generated using the various [Create Curves](#), and [Create Notes](#) buttons (3). The [Editing Tools](#) (4) help you draw, move, and edit correction objects.

Each correction object – or group of objects – can be adjusted to have its own independent Retune Speed, Vibrato adjustment, and Formant using the [Per Object Controls](#) (5).

The [Time Correction](#) (6) tools in Graph mode allow you to non-destructively and fluidly edit the timing of a musical performance.

Graph Mode Workflow

Below is a basic sample workflow in Graph Mode. For more detailed examples, please see the [Tutorials](#) section.

1. Track Pitch

Click the [Track Pitch](#) or [Track Pitch & Time](#) button, and begin playback to track your audio into Graph Mode (use Track Pitch & Time if you may wish to do any Time Correction edits). Auto-Tune will analyze the audio and display the detected pitch contour in red.

Note: In ARA2 instances of Auto-Tune Pro 11, Pitch and Time data will be tracked automatically upon loading the plug-in. For more information, see the [ARA2 Chapter](#).

2. Create Correction Objects

After tracking audio, Correction Objects will be created automatically, depending on the [After Tracking](#) setting in the Graph Mode Preferences.

You can also create Correction Objects manually using the [Create Curves](#), [Create Notes](#), or [Create Curves from Auto Mode](#) function, or draw them manually using the [Curve Tool](#), [Line Tool](#), or [Note Tool](#).

3. Edit Correction Objects

Use the [Range Tool](#), [Multi Tool](#), and [Split Tool](#) to edit the Correction Objects you've created.


4. Time Editing

If you've tracked your audio using the Pitch & Time function, you can use the [Point Tool](#) or [Region Tool](#) to edit the timing of your track.

Correction Objects

There are three types of Correction Objects in Graph Mode: Notes, Curves, and Lines.

Notes



Unlike Curves and Lines, which are continuously variable in pitch, each Note Object represents a single target pitch that persists for the duration of the Note Object.


Notes can be drawn with the [Note Tool](#), or created automatically using the [Create Notes](#) function.

After being created, a Note Object can be repositioned to a different note by clicking and dragging it up or down. If the [Play Tone When Moving Note Objects](#) setting is enabled in the [Graph Mode Preferences](#), a tone will play as you drag note objects up or down to let you know which note it was repositioned to.

If the [Snap To Note](#) setting is enabled in the [Quick Settings Menu](#), Note Objects will snap perfectly into place within pitch lanes that are included in the currently selected Key and Scale as you drag them up or down. To move Note Objects freely, hold down the Shift key while dragging them. (Or vice versa if the Snap To Note setting is disabled.)

After tracking pitch and time data, you can drag the left or right edges of a Note Object to adjust its length, thus shifting the start and end times of when pitch correction is applied to the note. For more information, see the [Point Tool](#) and [Region Tool](#) descriptions.

Curves




Curve Objects allow you to create and edit arbitrary and continuously variable pitch contours.

You may want to work with Curve Objects when you want the highest amount of control over a note's pitch adjustments at different points in time.

Curves can be drawn freehand using the Curve Tool or created automatically using either the [Create Curves](#) or [Create Curves from Auto Mode](#) function.

Curves are momentarily displayed in blue while being drawn to distinguish them from the red detected pitch contours and the green output pitch contours.

Lines




Lines are similar to Curves, except that they are made up of straight line segments.

Select the [Line Tool](#), then click anywhere on the Main Graph to create anchor points. Lines segments will be created between pairs of anchor points.

Double-click, or click in the same spot twice to end the operation with that point as the final point in the Lines object.

Like Curves, Lines are also displayed in blue.

Pitch Contours



There are three different types of color-coded pitch contours in Graph Mode: Red, Blue, and Green.

Red

Red contours represent the detected pitch of the audio, and appear after using the [Track Pitch](#) or [Track Pitch & Time](#) function. Because Red contours represent the pitch of the original, possibly out-of-tune audio, they cannot be edited or moved.

Blue

Blue contours (Curves) are a type of [Correction Object](#). They represent a continuously variable target pitch that Auto-Tune will tune the audio towards. They can be created using the [Make Curves](#) and [Create Curves from Auto Mode](#) functions, and can be drawn, moved and edited with the [Editing Tools](#).

Green

Green contours represent the output pitch that results from applying a Correction Object to the original audio.

Time Correction

The Time Correction tools in Auto-Tune Pro 11 are helpful for correcting moments where a vocalist is a little behind or ahead of the track's tempo.

We've combined an extremely high quality time-shifting algorithm with an intuitive user interface to make it quick and easy to correct timing errors or exercise your creative imagination.

In order to apply time correction, Auto-Tune must first create a copy of the audio you wish to edit. This is accomplished automatically with the [Track Pitch & Time](#) function.

Note: In ARA2 instances of Auto-Tune Pro 11, Pitch and Time data will be tracked automatically upon loading the plug-in. For more information, see the [ARA2 Chapter](#).

Once the audio has been tracked into Graph Mode, you can use the [Point](#) and [Region](#) tools to apply time-based editing.

The [Waveform Graph](#), located at the bottom of the plug-in window, can display the waveforms of both the input audio and the time-corrected audio, so you can easily compare them. To do this, select [Waveform Graph Shows: Dual Waveforms](#) in the Graph Mode [Preferences](#). This setting can be saved as the default Waveform Graph view if you prefer.

Non-Destructive Editing

Time edits in Auto-Tune Pro 11 are completely non-destructive because they occur on a copy of your audio, keeping the original audio intact.

You can switch off the [Enable Time Correction](#) setting at any point to return to your track's original timing. Or, to permanently delete your time edits, click the [Clear](#) button and choose "Time Changes".

Time Shifting Limits

The total amount of time compression or expansion that can be applied to a range of audio is limited to a 10:1 ratio. A range of audio can be expanded up to 10 times its original length or compressed down to 1/10th of its original length. Once that limit is reached, further compression or expansion is not possible, as noted in an onscreen reminder.

Managing Time Correction Data Files

Unlike the pitch data generated by the traditional [Track Pitch](#) function, which is always stored with the instances of Auto-Tune in your project, the audio recorded for time shifting by the [Track Pitch & Time](#) function is saved as one or more separate files elsewhere on your computer.

Before transferring a project that uses time correction from one computer to another, it is necessary to share the time edited audio files alongside the project file. If the next person who opens the project does not have the folder of time edited audio, pre-existing time edits will not be reflected in the session.

To help manage the recorded audio data required for time shifting, the [Quick Settings Menu](#) has a “[Move Data Folder](#)” setting and a “[Rename Data Folder](#)” setting. These settings let you to establish or move the location of the data files, or rename the folder where they’re stored.

Global Controls

The controls covered in this chapter are common to both Auto Mode and Graph Mode.


Auto-Tune Central



Click on the Antares logo to open **Auto-Tune Central**, a separate application used to manage license activations.

You may see a red badge on the Antares logo to notify you of any unread notifications from Auto-Tune Central. Typically, these notifications will let you know when a new update is available for the plug-in. Click on the Antares logo to open Auto-Tune Central, then open the Messages tab to view the notification.

Multi-View List



The **Multi-View List** shows you all the instances of Auto-Tune Pro 11 currently running in your DAW.

Select a track name to quickly open that instance of Auto-Tune within the same plug-in window. This saves you time opening and closing multiple plug-in windows, especially if you have several tracks of lead vocals, background vocals, etc. with their own instances of Auto-Tune.

Track names will sync from your DAW automatically in the Multi-View Instances List.

Note: *The Multi-View feature is not available on Audio Suite instances of Auto-Tune Pro 11 in Pro Tools.*

Undo



Click the **Undo** button to reverse your most recent edit, up to 99 steps.

Redo



Click the **Redo** button to restore the most recently undone edit.

Settings



Click the gear icon to open the [Quick Settings Menu](#).

The **Quick Settings Menu** is a dropdown list of settings you may want to toggle On/Off more frequently than those listed in the [Preferences](#).


Bypass



Click the **Bypass** button to disable Auto-Tune Pro 11 in your DAW. When bypassed, the Bypass button will appear de-illuminated.

Note: *The Bypass button only disables pitch correction created by Auto-Tune Pro 11. If present, time edits will still apply to maintain consistent timing with the source audio.*

Tracking




The **Tracking** knob determines how sensitive the Auto-Tune algorithm is, and is used to help Auto-Tune work more effectively.

In most cases, Tracking should be left at its default value of 50. However, please note the following:

- A noisier signal or a vocal performance that is unusually breathy may require a more 'relaxed' setting (higher Tracking value).
- If you're hearing artifacts such as clicks or pops, try setting the Tracking to a 'choosier' setting (lower Tracking value).


Input Type



Auto-Tune Pro 11 offers a selection of processing algorithms optimized for different vocal ranges and types of audio. **Input Type** options include:

- *Soprano*
- *Alto/Tenor*
- *Low Male*
- *Instrument*
- *Bass Instrument*

For the most accurate pitch detection and correction, choose the Input Type that best describes your audio.




After selecting an Input Type, a blue stripe on the top edge of the [Keyboard](#) will highlight the notes contained in the selected input type.

Note: *This function only applies to the Soprano, Alto/Tenor, and Low Male Input Types.*

While playing audio, the notes on the onscreen keyboard will also light up in blue as they're played. You can use these pieces of information in conjunction to help you decide if the selected Input Type is best for your audio.

Input Type – Learn



If you're not sure which Input Type would be best for your audio, use the **Learn** button to detect it automatically.

This feature uses Machine Learning to help you pick an input type that best matches the vocals on your track. For best results, play back 5 seconds of audio that best represents the typical vocal range of the track.

Note: *The learning process begins after you start audio playback.*

Follow the steps below to use the Learn function effectively:


1. Find a range of audio in your track that best represents the vocal range.
2. Click the Learn Button.
3. Start Playback for 5 seconds.

Key



The **Key** menu lets you select the key of the track you plan to process. The Key setting is used in combination with the Scale setting to determine the set of notes that the audio will be tuned to.

Scale



The **Scale** selection is used in combination with the Key selection to define the scale of the track you plan to process.

There are two sets of scales available– *Modern* and *Legacy*. The *Modern* scales are those that are commonly found in Western musical styles:

- Chromatic
- Major
- Minor
- Harmonic Minor
- Jazz Melodic Minor
- Dorian
- Phrygian
- Lydian
- Mixolydian
- Locrian
- Major Pentatonic

- Minor Pentatonic
- Blues
- Whole Tone
- Diminished

The *Legacy* selection of scales were present in Auto-Tune Pro X and earlier. These scales are generally considered to be more niche, including options such as Ling Lun, Just, Pythagorean, Arabic, and Indian.

You can change which set of scales to use as default with the [Scales](#) setting found in the [General Preferences](#) tab.

If you're not certain of the scale or key of your track, try using the [Auto-Key](#) plug-in in your DAW, or the [Auto-Key Mobile](#) application on your mobile device.

Another option is to set the Scale parameter to Chromatic, which will cause Auto-Tune Pro to always tune to the closest pitch in the 12-tone chromatic scale.

Auto-Key



The **Auto-Key** button enables Auto-Tune Pro 11 to receive Key and Scale information from the Auto-Key desktop plug-in or mobile app.

Auto-Key is a separate plug-in that automatically detects the key and scale of your track.


After successful detection, Auto-Key can send the key and scale information to multiple instances of Auto-Tune with a single click.

Note: *Auto-Key can only detect Major and Minor Keys/Scales. Other modern scales will need to be set manually within Auto-Tune Pro.*

Auto-Key is also available as a free application on mobile devices to detect and send key and scale information to Auto-Tune Pro 11. [Auto-Key Mobile](#) brings perfect pitch to your pocket!

For more information about the Auto-Key desktop plug-in, see its User Guide [here](#).


Preset Manager



Auto-Tune Pro features a collection of factory and artist presets, and a method for saving your own custom presets.

Use the left and right arrow keys to load presets in order. This is helpful for testing presets sequentially without navigating to the preset dropdown menu every time.

Preset Dropdown Menu



The **Preset Dropdown Menu** lists all of the presets available in Auto-Tune Pro 11.

Custom presets are listed in the User folder, and are located higher in the preset dropdown menu for easy access.

The Auto-Tune Pro 11 factory presets comprise a selection of natural sounding pitch correction.

We've created several presets to help you quickly get started with the [Harmony Player](#). These presets are all prefixed with "HP". Please note, the Harmony Player can only be enabled when a Major, Minor, or Chromatic scale is selected from the Scale dropdown menu.

Additionally, a number of artist presets showcase the creative effects possible with Auto-Tune Pro 11. They're listed alphabetically on the left side of the dropdown menu.

Preset Favorite Button



Click the thumbs up icon next to a preset name to add that preset to the Favorites folder.

Random Preset Button




Click on the dice icon on the preset manager to load a random preset. This is great for finding inspiration!

Preset Management Menu



Click on the three dots icon to open the **Preset Management Menu**. From here, you can save and delete custom presets, see where presets are stored on your computer, and reset your current preset to default.



In the Preset Folder on your computer, you can access the individual .xml files for each preset. This could be useful if you'd like to share one of your custom presets with a friend, for example.

To do this, you would copy the .xml file from the Preset Folder, and send it to the other party. They would then paste the .xml file into their Preset Folder, and the preset will become available to them in their instances of Auto-Tune Pro.

Auto/Graph Mode Switch




The **Auto/Graph Mode Switch** is used to toggle between Auto Mode and Graph Mode.

[Auto Mode](#) is optimized for real time, low latency performance, on stage or in the studio. You can control the parameters in real time using a MIDI controller, automate them using your DAW's automation features, or simply dial in your settings and let Auto-Tune take care of the rest.

[Graph Mode](#) allows you to make detailed pitch and time edits to individual notes and phrases using a pitch graph and a variety of editing tools.

Note: *Auto Mode and Graph Mode are two different audio paths, meaning audio can only be processed through one of the two at any given time. Settings made in Graph Mode can only be heard while you're in Graph Mode, and vice versa.*

Modern/Classic Mode Toggle



Classic Mode simulates an early Auto-Tune algorithm, and results in the fan favorite “Auto-Tune 5 sound.”

As new features were added to Auto-Tune over time (such as Formant Correction, Throat Modeling, and Flex-Tune), the Auto-Tune algorithm has evolved, and its sonic qualities have undergone subtle changes, with each Auto-Tune version having its own slightly different character.

Over the years, the sound of Auto-Tune 5 has developed something of a cult following among musicians, audio engineers and producers, perhaps due in part to its use on many iconic pop recordings. Due to popular demand, the Auto-Tune 5 sound is available in Auto-Tune Pro 11 via Classic Mode.


The sonic difference between Classic Mode and the modern sound of Auto-Tune Pro 11 is very subtle, but if you listen carefully, you may notice a slightly brighter quality on your vocals, and a more pronounced attack and transition between notes at faster Retune Speeds.

Classic Mode is available in both Auto Mode and Graph Mode.

Note: *The following features are disabled when Classic Mode is on:*

- *Formant*
- *Transpose*
- *Flex-Tune*
- *Time Editing*


Harmony Player Toggle

 Click to enable or disable the **Harmony Player**.

The [Harmony Player](#) lets you create and trigger up to 4 separate harmonies of your vocal, and blend them together.

Note: *The Harmony Player can only be used with Major, Minor, and Chromatic scales.*

Formant Correction

 A sound's formants are the resonant frequencies that result from the physical structure of whatever is producing the sound (e.g. the human mouth and vocal tract).


When a vocal is pitch-shifted by large intervals without formant correction, not only is the fundamental pitch shifted, but the formants are shifted as well. If not corrected for, this can result in an unnatural, chipmunk-like effect.

The shape of a singer's throat is a prime contributor to their vocal character. Formant correction in Auto-Tune Pro 11 uses a unique throat modeling technology to modify the sound of a voice by passing it through a physical model of the human vocal tract.

When **Formant Correction** is enabled, adjust the knob to specify the length of the modeled throat.

Another common way to use Formant Correction is to intentionally change the timbre of a voice as a special effect. Rotating the knob to the left will make the voice sound higher and thinner, providing a "chipmunk" effect. Alternatively, rotating the knob to the right will make the voice sound deeper and fuller.

Transpose

 In addition to any pitch correction applied by either Auto or Graph Mode, the **Transpose** control lets you shift the overall pitch of your performance over a two octave range (+/- one octave), selectable in semitone increments.

This control is useful for situations where you've transposed your backing tracks, for example, to a new key, and need to transpose your recorded audio to match.

In Auto Mode, this transposition is accomplished in real time. In Graph Mode, this function does not affect the [Output](#) pitch display, but provides overall transposition on top of any pitch shifting accomplished with the graph editing tools.

Conform To Scale




When the **Conform to Scale** feature is enabled, transposed notes created after adjusting the Transpose knob will always conform to the currently selected Key/Scale, up to -7 to +7 steps.

While disabled, notes will be transposed in chromatic intervals (-12 to +12 semitones) without regard to the currently selected Key/Scale. This means that the transposed notes may not necessarily be part of the currently selected Key/Scale, and may thus sound out of tune.

Note: *The Conform To Scale control is only available when using Major or Minor scales.*

Detune



The **Detune** parameter allows you to change the pitch reference of Auto-Tune Pro 11 from the default A = 440Hz. This is useful when working with an instrument or track that uses a different reference frequency.


Values can be displayed in Cents or Hertz (you can specify this in the Settings Menu). The range of adjustment is -100 cents to +100 cents.

Note: *Detune functions differently in Auto Mode and Graph Mode:*

- *In Auto Mode, the target pitch reference is shifted by the specified amount.*
- *In Graph Mode, the Detune knob shifts the position of the horizontal pitch reference lines in the [Main Graph](#), so that any correction objects created or adjusted relative to those reference lines will reflect the Detune setting.*

- *Detune will not automatically shift the position of correction objects that have already been created, so it's wise to make any needed adjustments to the Detune setting before creating your correction objects.*

Mix Knob



The **Mix Knob** adjusts the balance of processed and unprocessed signals. Turn the knob to 0 to hear only the unprocessed signal. At 100, you will only hear the processed signal.

In most cases, this knob should stay at 100, but it can be used as a creative effect when adjusted to a lower value. A chorus-like effect will be present when the unprocessed and processed signals are played simultaneously.

Note: *If present, time edits will be maintained even in the fully dry signal.*

Basic Auto Mode Controls




Auto Mode features two different interface views: the streamlined Basic View, which shows you only the most commonly used controls, and the more in-depth Advanced View, which includes detailed controls for the [Scale](#) and for adding [Vibrato](#).

This chapter will cover the controls that are visible in Basic view.


Note: Switching back to Basic View from Advanced View will hide the advanced controls, but will not disable them. You will still hear the results of your Advanced View settings when you return to Basic View.

Advanced




Click on the **Advanced** tab to toggle between Basic View and Advanced View.

After opening Advanced View, select whether to adjust the [Vibrato](#) or [Scale](#) controls.



Retune Speed



Retune Speed controls how rapidly the pitch correction is applied to the incoming audio. (*Units are in milliseconds.*)

Setting the Retune Speed to 0 will cause immediate changes from one pitch to another, and will completely suppress any vibrato or deviations in pitch.

If you'd like to recreate the iconic "Auto-Tune Effect", set the Retune Speed to 0.

For more natural sounding pitch correction, set between 10 and 50.

Larger values allow more vibrato and other interpretive pitch gestures, but decrease how rapidly corrections are made.

Flex-Tune




The **Flex-Tune** control allows you to preserve a singer's expressive vocal gestures, while still correcting an out of tune vocal.

When Flex-Tune is set to 0, Auto-Tune pulls every incoming note toward a target scale note. When Flex-Tune is engaged, it only applies correction as the performer approaches the target note.

As you move the control toward higher values, the correction area around the scale note gets smaller, and more expressive pitch variation is allowed through.

Humanize



The **Humanize** function allows you to add realism to sustained notes when using fast retune speeds.


One situation that can be problematic for pitch correction is a performance that includes both short and long sustained notes. In order to get the short notes in tune, you would need to set a fast Retune Speed, but this can cause sustained notes to sound unnaturally static.

Humanize applies a slower Retune Speed *only* during the sustained portion of longer notes, making the overall performance sound both in tune and natural.

Start by setting Humanize to zero, and adjust the Retune Speed until the shortest problem notes in the performance are in tune.

If sustained notes sound unnaturally static, increase the Humanize setting until they sound more natural.

Natural Vibrato



The **Natural Vibrato** control allows you to either increase or diminish the range of vibrato that is already present in your audio.


When the knob is at its default value of 0, the amount of vibrato present in the signal is neither increased or decreased.

If you turn the knob to the left of the center position (into the negative number values), the amount of vibrato is reduced.

Similarly, when you turn the knob to the right of the center position, the amount of vibrato is increased.

If you want to create *new* vibrato where it does not already exist, use the [Vibrato Controls](#) in Advanced View.

Pitch Display and Pitch Change Meter



Pitch Display

The Pitch Display shows you the letter name of the pitch that Auto-Tune Pro 11 is currently outputting.

This may be different than the pitch that it is detecting, if the detected pitch is not part of the current scale.

To see the pitch that is currently being detected in the incoming audio, look at the blue highlighted note on the keyboard.

Pitch Change Meter


The Pitch Change Meter (which wraps around the Pitch Display) shows you how much the pitch is being changed, measured in cents. When a detected pitch is sharp, the meter lights up orange, and wraps to the left. Flat pitches turn the meter blue, and wrap to the right.

For example, if the Pitch Change Meter has moved to the left to -50, it indicates that the input pitch is 50 cents too sharp, and Auto-Tune is lowering the pitch by 50 cents to bring the input back to the desired pitch.

Hold

Click and hold the Freeze icon underneath the Pitch Display while Auto-Tune is processing audio to pause both the Pitch Display and the blue detected pitch indication on the keyboard for as long as you hold down the mouse button.

The Keyboard




The **Keyboard** has three primary functions:

- Displays the currently detected pitch in real time.
- Highlights in blue to display the range of notes in the selected [Input Type](#).
- Allows you to specify the target-note behavior (On, Bypass, or Remove) for each note in specific octaves.


During playback, the detected pitch will be highlighted in blue on the Keyboard.

When you select any of the [Modern Scales](#) from the [Scale](#) dropdown menu, the notes on the Keyboard will be automatically added or removed to reflect the currently selected Key/Scale.

If you Remove or Bypass any keys on the Keyboard, the Key/Scale display will change to italics to reflect the modification:




On



When a note on the Keyboard is **On**, the keys will appear white or black (depending on which note it is), and input pitches that are closest to that note will be tuned to it.

Bypass




When a note on the Keyboard is set to **Bypass**, it will appear orange, and input pitches that are closest to that note will be passed through with no correction.

You might use Bypass if a performance has only one or two out-of-tune notes, and you want to only apply correction on those notes, or if it includes some expressive pitch gestures around one or more specific notes that you want to preserve with no modification.

Note: *Command/Ctrl + Click any key on the keyboard to reset the keys to their default state for the currently selected Key/Scale.*

Remove



When a note on the Keyboard is set to **Remove**, it will appear grey, and any incoming pitches that are closest to that note will be tuned to the next closest scale note instead.

Remove is useful in cases where a singer might be singing a pitch that is so far from the intended note that it's actually closer to another scale note.

For example, if the intended note is an F and the performer is actually singing something closer to an E, you may want to remove E from the scale, so that the singer will be tuned to F instead.

Note: *Command/Ctrl + Click any key on the keyboard to reset the keys to their default state for the currently selected Key/Scale.*

Keyboard Edit



When the **Keyboard Edit** switch is set to Remove, clicking on a key in the Keyboard will toggle it between Remove and On.

When it's set to Bypass, clicking on a key will toggle it between Bypass and On.

Latch



The Keyboard **Latch** control lets you customize how long keys will retain the Bypass or Remove state.

If the Latch is *enabled*, when you click a key to toggle the Bypass or Remove state, it will stay that way until you click on the key again to return it to its previous state. This is useful if you want the key to remain bypassed or removed for the whole song.

Alternatively, when the Latch is *disabled*, the Bypass or Remove state on a key will only be retained for as long as you hold the key down. This “clutch-style” approach is more suited for scenarios where you only want to change the state of a key momentarily.


Advanced Auto Mode Controls



Auto Mode features two different interface views: the streamlined [Basic View](#), which shows you only the most commonly used controls, and **Advanced View**, which includes all of the available controls. Advanced View is organized into two separate tabs for Vibrato Controls and Scale Controls.


Note: Switching back to Basic View from Advanced View will hide the advanced controls, but will not disable them. You will still hear the results of the Advanced View settings when you return to Basic View.

Vibrato Controls



The **Vibrato Controls** allow you to add a custom synthesized vibrato to your audio. Use them sparingly to add a touch of natural-sounding expression to a performance, or more aggressively for dramatic special effects.

Shape



The **Shape** menu allows you to choose the shape of the pitch modulation for your vibrato.

The Vibrato Shapes include:

Off

Select 'Off' if you don't want to create any vibrato.

Sine Wave

A sine wave changes smoothly from minimum to maximum and back again. This is the best choice for natural-sounding vibrato.

Sawtooth

Gradually rises from minimum to maximum and then drops instantaneously to minimum to start the cycle again.

Square


Jumps to maximum where it spends half of the cycle and then jumps to minimum for the remaining half of the cycle.

Rate



The **Rate** control sets the speed of the vibrato in Hz.


Delay



Delay sets the amount of time (in milliseconds) between the beginning of a note and the onset of vibrato.

This control is useful for sustained notes where you want the beginning of the note to have no vibrato, then have the vibrato come in later.

Onset Rate



Onset Rate sets the amount of time (in milliseconds) between the onset of vibrato and the point at which the vibrato reaches the full amounts set in the Pitch, Amplitude and Formant Amount settings.

Variation




Variation sets the amount of random variation that will be applied to the Rate and Amount parameters on a note to note basis. This setting is useful for “humanizing” the vibrato by adding random deviations in the behavior of the vibrato.

Pitch Amount



Pitch Amount sets the width of the vibrato in cents.

Amplitude Amount



Amplitude Amount sets the amount that the loudness changes.

For the most realistic vibrato, the amount of amplitude change should be substantially less than pitch change.

Formant Amount



Formant Amount sets the amount of formant variation in the vibrato.

Scale Controls



The **Scale Controls** are used to create custom scales or to modify any of the preset scales selected in the Scale menu. It shows each of the notes of the currently selected scale, along with a Bypass and Remove button for each note.

Each scale retains its own edits independent of the other scales. For example, if you select C Major in the Key and Scale menus and Remove or Bypass certain notes and then change to C Minor and make other edits, when you return to C Major your previous edits associated with C Major will be restored.

Changes made to the Scale Controls affect *all* octaves of each note in the scale, and will also be displayed on the Keyboard. Changes made on the Keyboard only affect that specific octave, and will not be reflected in the Scale Control section.

Bypass



If a note is set to **Bypass**, input pitches that are closest to that note will be passed through with no correction.

You might use Bypass if a performance has only one or two out-of-tune notes, and you want to only apply correction on those notes, or if it includes some expressive pitch gestures around one or more specific notes that you want to preserve with no modification.

Remove



If a note is set to **Remove**, then that note is removed from the current scale, and any incoming pitches that are closest to it will be tuned to the next closest scale note instead.

There may be situations where you want to use a scale that is unavailable in the provided list of scales- the Remove function can be used to create your own custom scale based on one of the built-in [Modern or Legacy scales](#).


Remove is also useful in cases where a singer might be singing a pitch that is so far from the intended note that it's actually closer to another scale note. For example, if the intended note is an F and the performer is actually singing something closer to an E, you may want to remove E from the scale, so that the singer will be tuned to F instead.

Cents Display



The number under each note in the **Cents Display** is that note's interval, in cents, from the root note of the scale.

Set Major/Set Minor



The **Set Major** and **Set Minor** buttons allow you to quickly generate a major or minor scale from any scale with more than 7 notes, by automatically removing the notes that don't belong to the major or (natural) minor scale.

Note: These buttons are only available when a Chromatic scale is selected.

Set All



The **Set All** button sets all of the notes of the current scale to on, in both the Scale Controls and the Keyboard. This is a quick way to return the scale to its default setting.

Bypass All



Bypass All sets all notes in the current scale to Bypass.

Remove All




Remove All sets all notes in the current scale to Remove.

Left/Right Scroll



The **Left and Right Scroll** buttons become available whenever a scale with more than 12 notes is currently in use. In this case, the arrows are used to scroll the advanced scale blocks left or right to display all of the relevant information for every note in the scale.


Ignore Vibrato



The **Ignore Vibrato** function is designed to help Auto-Tune identify pitches correctly when a performance includes vibrato so wide that it approaches adjacent notes (e.g. if a singer is singing a C with a vibrato so wide that it is sometimes closer to a C#).

If you hear a rapid alternation between two notes when you want to hear a single note with a wide vibrato, try turning this setting on.

MIDI Functions



There are two **MIDI Functions** in the Scale Controls tab for handling incoming MIDI note data: [To Notes](#) and [Learn Scale](#). You can also use a MIDI controller to adjust many Auto-Tune Pro 11 parameters in real time.

See the [MIDI Control Preferences](#) section to learn how to assign Auto-Tune Pro 11 parameters to your MIDI controller.


Use the **To Notes** function if you want to use MIDI to control the specific pitch that your audio is being tuned to in real time. Use the **Learn Scale** function if you want to use MIDI instead of the Scale Controls and onscreen Keyboard to define the scale that your audio will be tuned to.

In order to make use of the MIDI capabilities in Auto-Tune Pro 11, you will need to route a MIDI source to Auto-Tune Pro 11. This could be an external controller, such as a MIDI keyboard, or it could be a MIDI track within your host application (DAW).

The procedure for routing MIDI to an audio plug-in will vary depending on what DAW you are using, so please see your DAW's manual or help pages for more information about how to do this.

Note: MIDI routing instructions for [Pro Tools](#) and [Logic Pro X](#) are also available in the Antares knowledge base.

To Notes

A dark grey rectangular button with rounded corners and a thin white border, containing the text "To Notes" in white.

With **MIDI: To Notes**, you can perform a melody in real time on a MIDI keyboard or play it from a MIDI track, and Auto-Tune Pro 11 will tune your audio to whatever MIDI notes are on at any given time.

If you're using a MIDI keyboard, this means that your audio will be tuned to the notes corresponding to whatever keys you are currently holding down.

If no MIDI notes are on at any given time, the audio will pass through without being tuned.

Learn Scale


A dark grey rectangular button with rounded corners and a thin white border, containing the text "Learn Scale" in white.

The **MIDI: Learn Scale** function allows you to play a melody or chords from a MIDI keyboard or MIDI track and have Auto-Tune construct a custom scale for you containing only those notes.

Clicking the Learn Scale button will remove all notes from the current scale. Individual notes are then turned back on based on incoming MIDI data. The new scale settings will be displayed on both the Keyboard and in the Scale Control tab.

If no MIDI note-on messages are received, the audio will pass through without being tuned.

All Octaves

A dark grey rectangular button with rounded corners and a thin white border, containing the text "All Octaves" in white.

If **All Octaves** is on, any incoming MIDI notes will affect all octaves of each note. Otherwise, they will only affect the notes in the specific octaves in which they are played.

The All Octaves button applies to both the To Notes and Learn Scale functions.

MIDI Mapping

Many parameters in Auto-Tune Pro 11 can be controlled in real time with any hardware or software MIDI controller that sends MIDI CC (continuous controller) messages.

For a full list of controls that can be mapped to your MIDI hardware, please refer to the [MIDI Mapping Master List](#) at the end of this document.


To start the MIDI mapping process, simply right click on the control you want to map, and the mapping menu will appear:



You will also need to route the MIDI to Auto-Tune Pro 11 within your host application (DAW). The procedure for routing MIDI to an audio plug-in will vary depending on what DAW you are using, so please see your DAW's manual or help pages for more information about how to do this.

Note: MIDI routing instructions for [Pro Tools](#) and [Logic Pro X](#) are also available in the Antares knowledge base.

MIDI Learn




When you click on the MIDI **Learn** option, a blue ring will appear on the control while it “listens” for MIDI input. At this point, you should press or rotate the button or knob on your MIDI hardware that you want to link to the control.

After successfully learning the MIDI CC message from your MIDI hardware, the UI will return to normal, and you will be able to adjust the control using the button or knob you assigned it to on your MIDI hardware.

Note: The MIDI Learn function is unavailable and will be greyed out in VST3 instances of Auto-Tune Pro. Please use the MIDI CC option instead for VST3 instances.

MIDI CC



The **MIDI CC** option is a way to manually assign a control in Auto-Tune Pro to your MIDI hardware.

MIDI CC stands for MIDI “Continuous Controller”.

When you interact with your MIDI hardware, whether it's a button, knob, slider, or mod wheel, you send a MIDI CC channel-specific value (from 0 - 127) to the host. Check your MIDI controller's documentation for information about what MIDI CC value is sent by each control.

After selecting the MIDI CC option from the MIDI mapping menu, you will see a long list of MIDI CC values to assign to the control in Auto-Tune Pro. Doing this will temporarily overwrite your MIDI hardware's default MIDI CC value.

Clear

Click the **Clear** button to remove the linked MIDI CC value from a control in Auto-Tune Pro. This will reset the MIDI mapping you've assigned, and the MIDI CC value will return to default.

Harmony Player Controls




The **Harmony Player** is a brand new section of creative controls added to Auto-Tune Pro, starting in version 11. With the Harmony Player, you can create and trigger up to 4 individual harmonies (called Harmony Voices) based on your input vocal. You can adjust their controls individually, then blend their outputs together.

You can play harmonies in your track by creatively bringing Harmony Voices in and out with their individual Trigger buttons.

All of the controls in the Harmony Player can be mapped to MIDI hardware, making it easy to play harmonies during a live performance.


Important Note: The Harmony Player can only be used with Major, Minor, or Chromatic scales.

Mixer



In Mixer Mode, you can adjust the [Formant](#), [Width](#) or [Pan](#), and [Level](#) knobs for each Harmony Voice individually.

Input



The **Input** buttons allow you to either Mute or Solo the input signal.




Click the **Mute Input** button to silence the input audio. Doing so will allow you to hear only the harmonies produced by the Harmony Player, without the original signal.



Similarly, enabling the **Solo Input** button allows you to hear only the input signal and any individual Harmony Voices that are also soloed.

Harmony Interval



Use the **Harmony Interval** dropdown menu to select how generated harmony intervals are calculated.

In **Scale Interval** mode, the harmonies you select will always conform to the currently selected Key/Scale, so that any harmonies generated will result in notes that belong to that Key/Scale.

In **Fixed Interval** mode, the harmonies generated are chromatic intervals based on the incoming note without regard to the currently selected Key/Scale. This means that the harmony notes generated may not necessarily be part of the currently selected Key/Scale.

Pan




Select the **L / R** option to pan Harmony Voices to the Left or Right within the stereo mix.

Note: *This control is only available on stereo tracks, or when you instantiate Auto-Tune Pro as 'Mono to Stereo'.*

Alternatively, select the **Width** option to widen the stereo width of the Harmony Voices.


Naturalize



Use the **Naturalize** knob to specify how much of the natural vibrato and pitch variation from the Input Voice will be applied to the generated Harmony Voices.

Lower settings will remove some of the original vibrato and pitch variation from the Harmony Voices, and higher settings will allow more of it through.

Transition Time



The **Transition Time** knob lets you adjust the amount of time (in milliseconds) it takes for Harmony Voices to transition from one note to the next during legato phrasing.

Higher values will result in slower note transitions.


Pitch Variation



The **Pitch Variation** control lets you select the range of random variation in pitch applied to each Harmony Voice.

Higher values will result in a larger maximum variation, but the specific amount of variation applied to each voice is randomized, and will be different for each voice.


Timing Variation



The **Timing Variation** control lets you select the range of random variation in timing applied to each Harmony Voice.

Higher values result in a larger maximum variation, but the specific amount of variation applied to each voice is randomized, and will be different for each voice.

Harmony Voice Modules



The Harmony Player lets you create and trigger up to 4 individual harmonies (called **Harmony Voices**) based on the input vocal, post Auto-Tune processing.

The controls for each Harmony Voice are organized into their own modules within the Harmony Player section. You can adjust their controls individually, then blend their outputs together.

Important Note: The Harmony Player can only be used with Major, Minor, or Chromatic scales.

Solo



Click the **Solo** button to listen to an individual Harmony Voice. You can also solo more than one voice module at a time to hear how they sound together.

Interval



Use the **Interval** dropdown menu to select the interval for this Harmony Voice.

In **Scale Interval** mode, the intervals will be harmonies that will always conform to the currently selected Key/Scale, so that any harmonies generated will result in notes that belong to that Key/Scale.

In **Fixed Interval** mode, the interval options are chromatic. This means that the generated harmonies will be based on the incoming note without regard to the currently selected Key/Scale. In other words, the harmony notes generated may not necessarily be part of the currently selected Key/Scale.

Trigger Latch



Enable the **Latch** button to turn the associated Harmony Voice on or off when you click on the Trigger button in the voice module.

When the Latch control is disabled, the Harmony Voice will only sound for as long as you hold down its Trigger button.

Formant



The **Formant** knob can be adjusted to make a Harmony Voice sound deeper or higher (not to be confused with the pitch of the note.)

Settings lower than 100 will make the voice sound deeper, while settings higher than 100 will make the voice sound higher.

Subtle formant adjustments can be used to correct artifacts, and make the Harmony Voice sound more natural. Extreme settings are best used for creative effects.

Pan



If the [Pan](#) selector is set to *L / R* in the Harmony Player controls, you can use this knob to adjust the placement of each Harmony Voice within the stereo field.

Width



If the [Pan](#) selector is set to *Width* in the Harmony Player controls, you can use this knob to adjust the stereo width of each Harmony Voice.

Each Harmony Voice starts out as a mono signal. As you move the Widen knob from left to right, the sound becomes bigger and wider.

When the knob is all the way to the left, the signal is its original mono state, then gets wider as you rotate the knob clockwise.


Level



Use the **Level** knob to change the volume level for each Harmony Voice. This control is helpful for blending the harmonies into your track.

If the Harmony Voice starts to clip, the clipping indicator will turn red. Adjust the level to a lower value, and click on the clipping indicator to reset it.


Trigger



Click the **Trigger** button to turn the Harmony Voice on or off.

It will only be enabled for as long as you hold down the Trigger button, unless the voice module's [Trigger Latch](#) is enabled.

Trigger All Button




Click the **Trigger All** button to turn all Harmony Voices on or off at the same time.

The Harmony Voices will only be enabled for as long as you hold down the Trigger All button, unless the **Latch** button is enabled.

Latch

While the **Trigger All Latch** is enabled, all Harmony Voices will be turned on or off at the same time when you click on the Trigger All button.

Envelope Controls



The **Envelope** module lets you adjust the Attack and Release times of Harmony Voices that are triggered on/off manually.

These controls are helpful for turning normal-sounding harmonies into interesting creative effects.

Note: If the [Trigger Latch](#) is enabled on a Harmony Voice module, the Envelope controls will not be applied to that module.

Attack




Use the **Attack** knob to adjust the Attack time in milliseconds.

The Attack time determines the amount of time it takes for the Harmony Voices to ascend from their initial silence to their peak amplitude.

Note: This control is only active when the [Trigger Latch](#) is turned off, and the Harmony Voice is triggered manually.

Release



Use the **Release** knob to adjust the Release time in milliseconds.

The Release time determines how long it takes for the Harmony Voices to fade to silence.

Note: This control is only active when the [Trigger Latch](#) is turned off, and the Harmony Voice is triggered manually.


Equalizer Controls



The **Equalizer** module lets you select one of three EQ bands to apply to the Harmony Mix, and adjust their controls to help the generated harmonies blend more seamlessly into the mix.

Note: Only one EQ band can be applied at any given time.

High Pass, Band Pass, Low Pass Filter Selector




Use the EQ Selector buttons to choose which EQ band to apply to the Harmony Voices.

The first option applies a **High Pass Filter** to the Harmony Mix. This is useful for filtering out unwanted 'boominess' caused by low end frequencies.

The middle option applies a **Parametric** EQ band to the Harmony Mix. The three controls for this filter are helpful for finding and eliminating unwanted resonant frequencies in the mix.


The last option applies a **Low Pass Filter** to the Harmony Mix. If the generated harmonies sound too present in the mix, this control is helpful for filtering out unwanted high end brightness.

Frequency



All three EQ band options have a **Frequency** control that you can adjust to set the frequency of the filter. Use this knob to specify which frequencies you want to address with the EQ band.

Slope



The **Slope** determines the “steepness” of the filter.

For example, a 6dB/octave slope is a gradual decline, useful for gentle shaping, while a 24dB/octave slope provides a more dramatic curve.

The slope buttons are present only on the High Pass and Low Pass filters.

Q



With the Band Pass filter, you can adjust the bandwidth knob (**Q**) to determine the sharpness (or width) of the filter.

This allows you to attenuate or boost a very narrow or wide range of frequencies within the band.

A higher setting will result in a sharper (narrower) filter band that is helpful for eliminating specific frequencies/resonances in the harmony mix.

Level



Use the **Level** knob to adjust the gain level of the Band Pass Filter in dB.


Gate & Width Controls



The **Gate** module automatically triggers Harmony Voices alongside the presence of incoming audio.

This allows you to work creatively by having the harmonies come in and out in time with external audio signals.


Threshold



The Gate **Threshold** determines the level at which the Gate automatically triggers the Harmony Voices.

This control is used in conjunction with an internal or external audio signal (via Side Chain) to determine when harmonies are triggered.

Side Chain



Use the Side Chain Selector buttons to choose Internal or External side chain.

Int

When the **Internal** Side Chain option is selected, the Harmony Player will listen to the audio signal from the *original input* vocal, in conjunction with the Threshold, to bring the Harmony Voices in and out in time with the lead vocal.


Important Note: If the *Internal Sidechain* button is selected and engaged, and the [Mute Input](#) button is enabled, there will be no audio output from Auto-Tune Pro.

Ext

When the **External** Side Chain option is selected, the Harmony Player will listen to an audio signal on a *separate* track in your DAW, in conjunction with the Threshold, to bring the Harmony Voices in and out in time with the lead vocal.

This option can be used creatively to have the Harmony Voices come in and out alongside another vocal or instrument track.

Width




The **Width** knob adjusts the overall stereo width of the Harmony Player voices. Reducing or expanding the stereo width of the Harmony Voices can help them blend into the mix more seamlessly.

The leftmost position on the Width knob collapses the stereo image, essentially converting it to a mono signal.

The center position preserves the original stereo width created by the individual [Pan](#) or [Width](#) settings of each of the four Harmony Voices.

The rightmost position expands the stereo image beyond its original width, creating an even wider image.

Graph Mode Controls




While Auto Mode is great for making quick adjustments during real time performances, **Graph Mode** gives you the freedom to make precise pitch and time adjustments to individual notes and phrases.

A variety of tools help you tweak each and every word until they're just right. In Graph Mode, you have the option to adjust the tuning of each note separately, without relying on Auto Mode to apply a general tuning to the whole track.

Main Graph and Waveform Graph

Main Graph



The **Main Graph** is where pitch and time editing takes place in Graph Mode. After tracking pitch or tracking pitch and time, the Main Graph will display the waveform of the audio and the detected pitch contour of the audio ([red curves](#)).

It will also display any pitch correction objects that you create, and the contour of the resulting output pitch ([green curves](#)).

The horizontal grid lines represent scale pitches. The vertical lines represent time units, which may be either minutes and seconds or bars and beats, depending on the [Time Display](#) setting.


Toolbar Show/Hide Buttons



The two buttons in the top left corner of the Main Graph allow you to show or hide the [Global Controls](#) bar and the Graph Mode Toolbar respectively.

It may be helpful to hide one or both of these toolbars to give yourself extra vertical space while working in Graph Mode.

Waveform Graph



The **Waveform Graph** is the smaller graph below the Main Graph used to navigate and zoom in the Main Graph.

When using Time Correction, you can view the original and time edited waveforms side by side for comparison. To do this, select [Waveform Graph Shows: Dual Waveform](#) in the Graph Mode Preferences.


The top waveform represents tracked audio and any time edits applied to it. The bottom waveform shows the original 'source' audio, without reflecting any time edits.



The Waveform Graph can be shown and hidden by clicking the show/hide icon in the lower right corner of the Main Graph.

If you prefer to have a little more room in the Main Graph, and only open the Waveform Graph as needed, you can set the Waveform Graph to be hidden by default in the [Graph Mode Preferences](#).

All/Tie Switch




When set to **All**, the Waveform Graph will display all of the currently tracked audio.

This is useful for quickly locating and selecting various portions of audio or navigating through the duration of your track.


When set to **Tie**, the Waveform Graph position and zoom setting follow the position and zoom setting of the Main Graph.

Zoom States



The **Zoom State** buttons allow you to quickly toggle between different levels of zoom in the [Main Graph](#).

To save the current zoom setting, hold down the Option (Mac) or Alt (Windows) key and click on one of the Zoom State buttons.



The **Zoom Outline** appears in the Waveform Graph to give you a clear view of the zoom range you have selected, and which part of the waveform you're looking at in the Main Graph.

The Zoom Outline has a top and a bottom half, each with their own unique interactions.

If the [Use Custom Cursors for Editing Tools](#) preference is enabled, the top and bottom halves of the Zoom Outline will be indicated by changes in your mouse cursor. The normal 'arrow' cursor means you are in the *top half* of the Zoom Outline, while a magnifying glass cursor indicates that you are in the *bottom half*.

You can interact with the top and bottom halves of the Zoom Outline in the following ways:

- Click and drag anywhere on the [Waveform Graph](#) to quickly reposition the Zoom Outline to that location.
- Click and drag inside the *top half* of the Zoom Outline to move the zoom range left or right.
- Click and drag within the *bottom half* of the Zoom Outline to reset the zoom range.
- To resize the zoom range, click and drag either edge of the Zoom Outline to expand or contract it.


Pitch Tracking and Correction Objects

Track Pitch or Pitch & Time



To begin editing in Graph Mode, you'll first need to track the audio into Auto-Tune Pro 11 so that it can be analyzed. To do that, click on the **Track Pitch** or **Track Pitch & Time** button, then begin playback.

The first time you open Graph Mode, you will be prompted to record audio into the graph via the pop-up window pictured below:




Alternatively, you can open Auto-Tune Pro 11 as an [ARA2](#) plug-in to track pitch and time data automatically.

Auto-Tune will read and analyze the pitch of the incoming audio. If you've chosen Pitch & Time, it will also create a copy of the audio, so that you can apply Time Correction edits non-destructively.

If you think you may want to make use of the [Time Correction](#) features, use Track Pitch & Time. If you know that you won't be doing any Time Correction, we recommend using Track Pitch for optimum performance and more efficient use of disk space.

After tracking audio, Note Objects will be created automatically by default. You can select which type of Correction Object is created with the [After Tracking](#) preference in the Graph Mode Preferences.

Create Curves



The **Create Curves** buttons allow you to create pitch correction objects known as [Curves](#) from the detected pitch contour data.

The Curve Objects can then be dragged and stretched for very precise pitch correction.

Note: *If a range has been selected with the [Range Tool](#), the Create Curves action will only create Curve Objects within the selected range.*

Create Curves From Audio

The **Create Curves From Audio** button will generate pitch correction Curves based on the detected pitch contour data.


Create Curves From Auto Mode

The **Create Curves from Auto Mode** function allows you to use your Auto Mode settings as a starting point for further editing in Graph Mode.

It does this by creating [Curves](#) objects that exactly match the pitch correction that would result from processing the audio with the current Auto Mode settings.

To use Create Curves from Auto Mode, switch over to Auto Mode and adjust the settings as needed. Then, switch back to Graph Mode and click the Create Curves from Auto Mode button to create the Curve objects.

Create Notes



The **Create Notes** buttons are used to automatically create Note Objects based on tracked audio or with MIDI input.

Note: If a range has been selected with the [Range Tool](#), the Create Notes action will only create Note Objects within the selected range.

Create Notes From Audio

Create Notes From Audio generates Note Objects based on an analysis of tracked audio. Auto-Tune will analyze your audio and create Note Objects wherever a note onset is detected.

Try adjusting the [Density](#) control to make the Create Notes function more or less likely to interpret a change in pitch as a new Note Object that gets created. After Note Objects are created, they can be edited and moved using the [Editing Tools](#).

Create Notes From MIDI


Create Notes From MIDI uses MIDI note data to define target pitches in Graph Mode. It will create Note Objects based on MIDI note data that has been tracked in the selected region.

To use Create Notes from MIDI:

1. Route a MIDI source to Auto-Tune Pro 11. This could be a MIDI controller, or a MIDI track within your project. The procedure for routing MIDI to an audio plug-in is different in various DAWs, so consult your DAW's documentation.
 - a. *Note: MIDI routing instructions for [Pro Tools](#) and [Logic Pro X](#) are also available in the Antares knowledge base.*
2. Click the Track Pitch or Track Pitch & Time button and begin playback to track audio and MIDI data into Graph Mode. If [Show Tracked MIDI](#) is enabled in the Graph Mode Settings, the MIDI data will be drawn on the Main Graph.

3. Click Create Notes, and choose Create Notes From MIDI. Note Objects will be created according to the tracked MIDI data.

Density



When Auto-Tune analyzes the input pitch for the purpose of creating Note Objects, it makes decisions about what constitutes a note and where the boundaries between notes are.


The **Density** control lets you customize this process to suit the material that you're working with.


When Density is set to a higher value, Auto-Tune will be more likely to interpret changes in pitch as new note events, rather than deviations or expressive gestures within a single note.

Density is only active after tracking pitch, and applies only to the region of the graph that is currently selected.


Note: *If the density value is changed after selecting the mid section of a long Note Object, it will split into separate Note Objects.*

See below for screenshots that compare the results of *low* and *high* Density settings:





Per Object Controls



Graph Mode features a selection of **Per Object Controls** to fine tune the settings of individual notes or phrases.


These powerful customization tools help you adjust the tuning behavior for individual phrases or words of a vocal.

The Per Object Retune Speed, Vibrato, and Formant knobs function identically to their Auto Mode counterparts, but the key difference is that their settings are only applied to the selected correction objects. These controls are helpful for giving different sections of your track their own individual Retune Speed, Vibrato, and/or Formant settings.

You can quickly adjust the Per Object settings of individual correction objects (or hold Command/Ctrl to select multiple correction objects) by clicking on them with the [Arrow Tool](#), then holding the **keyboard shortcuts** listed below:

- Hold **R** key + drag/scroll mouse, to adjust Retune Speed.
- Hold **V** key + drag/scroll mouse, to adjust Vibrato.
- Hold **F** key + drag/scroll mouse, to adjust Formant

Retune Speed



As in Auto Mode, the **Retune Speed** in Graph Mode controls how rapidly the pitch correction is applied to the incoming audio.

However, while tuning in Auto Mode, the Retune Speed parameter uses the current scale settings to determine the target pitch.

In Graph Mode, the target pitch is defined by correction objects (Curves, Lines, and Notes).

In Graph Mode, you can assign different Retune Speeds to individual correction objects, or to select a group of objects and assign them all the same Retune Speed.

Any adjustments to the Retune Speed control in Graph Mode will apply to all correction objects that are currently selected. If no objects are selected, the control is disabled.

To recreate the “[Auto-Tune Effect](#)”, set the Retune Speed to 0. A setting between 10 and 50 is typical for more natural sounding pitch correction. Larger values allow more vibrato and other interpretive pitch gestures, but slow down how rapidly corrections are made.

Vibrato




The **Vibrato** control allows you to either increase or diminish the range of vibrato that is already present in your audio.

In Graph Mode, you can apply different vibrato adjustment values to individual correction objects (Curves, Lines, and Notes).

Any changes to the Vibrato control will apply to all correction objects that are currently selected. If no objects are selected, the control is disabled.

Formant




The shape of a singer’s throat is a prime contributor to their vocal character. The formant correction in Auto-Tune Pro 11 utilizes a unique throat modeling technology to modify the sound of a voice by passing it through a physical model of the human vocal tract.

The **Formant** control lets you specify the length of the modeled throat.

The Graph Mode Formant control and the global Formant control basically do the same thing, except that Throat Length can be applied differently to individual correction objects in Graph Mode, and the Formant control is applied to all incoming audio.


Any changes to the Formant control will apply to all correction objects that are currently selected. If no objects are selected, the control is disabled.

Selection Tools




The following **Selection Tools** exist in a floating display on the right corner of the [Main Graph](#).

Select All



The **Select All** button selects all Correction Objects in the Main Graph.

Clear



Clicking the **Clear** button opens a menu with the following options:

Pitch Correction Objects

This option deletes all existing pitch correction objects (Curves, Lines and Notes). It does not delete detected pitch information or time correction edits.

Time Changes

This option deletes all time correction edits. It does not delete detected pitch information or pitch correction objects.


Both Pitch and Time

This option deletes all pitch correction objects and time correction edits. It does not delete detected pitch information.

All Data (Cannot Undo!)

This option deletes all pitch correction objects, time correction edits, and detected pitch information. It cannot be undone.

Copy




The **Copy** button copies selected objects to the clipboard.

Cut



The **Cut** button removes any selected objects from the graph and copies them to the clipboard.

Paste




The **Paste** button can be used to paste correction objects from the clipboard to anywhere on the graph.

To paste objects from the clipboard:


1. Navigate to the general area where you want to paste the objects.
2. Click the Paste button.
3. Press and hold the mouse button.
4. While holding down the mouse button, drag the objects to the exact location where you wish to paste them.
5. Release the mouse button to complete the paste.

Drawing Tools



The following drawing tools are used to manually create correction objects in the [Main Graph](#). This is helpful in situations where you want more precise control over the locations, durations, and shapes of correction objects.

Line Tool



The **Line Tool** is used to draw straight, multi-segment [Lines](#) (correction objects) on the Main Graph.

To draw a line, follow the steps below:

1. Select the Line Tool and click anywhere on the Main Graph to create the first anchor point.
2. Click again to set a second anchor point and define the first segment of your pitch contour.
3. Continue clicking and defining anchor points until your desired contour is complete.
4. End the process by double-clicking on the final anchor point or pressing Esc on your keyboard.


If the [Snap To Note](#) setting is *enabled* in the Graph Mode Preferences, each segment will automatically snap to the nearest scale note. Holding the Shift key on your keyboard while drawing a line temporarily toggles the state of the Snap To Note setting.

In other words, if Snap To Note mode is *disabled*, holding Shift will enable it for as long as Shift is pressed and vice versa – if Snap to Note is *enabled*, holding shift will disable it for as long as Shift is pressed.

To make a line perfectly horizontal, hold down Option (Mac) or Alt (Windows) on your keyboard while drawing.

To delete the last anchor point entered, press Delete (Mac) or Backspace (Windows) on your keyboard. You can delete anchor points repeatedly back to the first anchor point.


Curve Tool



The **Curve Tool** is used to draw [Curves](#) (correction objects) on the Main Graph. To draw a curve, select the Curve Tool, then click and drag anywhere on the Main Graph.

The [Snap To Note](#) setting does not affect the Curve Tool.

Note Tool




The **Note Tool** is used to draw [Notes](#). Once you've created a Note, you can drag it up or down using the Multi Tool.

New Notes are always drawn exactly on the scale note graph lines or lanes, regardless of the [Snap To Note](#) setting.


If you want to create a note that is offset from a [Pitch Lane or Line](#), first draw a note on the nearest lane or line, ensure that Snap To Note is *Off*, and use the Multi Tool to move the Note to the desired pitch. Alternatively, hold down the Shift key while dragging a Note Object to toggle the behavior of the Snap To Note setting.

Editing Tools



The **Editing Tools** help you interact with existing correction objects and navigate the [Main Graph](#). These are your primary tools for executing various tasks in Graph Mode.

If the [Use Custom Cursors For Editing Tools](#) preference is enabled, different cursor shapes will be displayed in the Main Graph to help you select ranges and grab and drag correction objects (e.g., the object cursor, the anchor point cursor, etc.). All custom cursors are displayed in context in the screenshot below:



Arrow Tool



The **Arrow Tool** is a smart, multi-function tool that is used to move, select, and edit existing correction objects (Lines, Curves, or Notes). It serves a variety of purposes for different types of objects:

Line and Curve Objects:

- Click on a [Line](#) or [Curve](#) to select it.
- Click on the anchor point to select just the anchor point.
- Click and drag a Line or Curve to move it up or down.
- Click and drag an anchor point to move just the anchor point.
- Double-click anywhere on a line to create a new anchor point. Double-click on an existing anchor point to delete it.

Note Objects:

- Click on a [Note](#) to select it.
- Click and drag near the center of a Note Object to move it up or down.
 - When moving Note Objects with the Multi Tool while [Snap to Note](#) is enabled, the Note Objects will snap to the nearest scale tone.
 - Holding down the Shift key on your keyboard while editing will temporarily toggle the state of Snap to Note to its other state.
- Click and drag near the ends to extend or shorten it horizontally.
 - Extending or shortening Note Objects adjusts the start /end time of when pitch correction is applied.

Multiple Objects:

- Click away from any existing correction objects to deselect all objects.
 - This is useful if you want to select a single anchor point or line segment.
- Click and drag left or right to select all correction objects, anchor points, or line segments within that selection range.
 - Press and hold the Option/Alt key while dragging to move the selected correction objects in time as well as pitch.
 - The cursor's appearance will change to reflect whether you're moving the correction objects on one or both axes.
 - **Note:** *this movement may be restricted by adjacent objects, preventing currently selected objects from moving on top of existing objects.*
- Command/Ctrl + Click on multiple objects to select them all as a group
 - Command/Ctrl + Click an already selected object to de-select it

If [Play Tone When Moving Notes](#) is turned on in the Quick Settings Menu, you'll hear a reference pitch play when you drag Note Objects up or down.

Range Tool



Drag the **Range Tool** in the [Main Graph](#) to highlight a range of time, and any correction objects that are in that area.

If a range is selected with this tool, correction objects generated via the [Create Curves](#) and [Create Notes](#) tools will only be generated within that range.


The range tool is also useful for selecting portions of phrases to apply precise pitch correction, as described in [this tutorial](#).

Double-click with the Range tool in either the Main Graph or [Waveform Graph](#) to highlight the range of all currently tracked audio.

With the [All/Tie](#) switch next to the Waveform Graph set to All, use the Range tool to navigate from one location to another in the Main Graph.


With the All/Tie switch next to the Waveform Graph set to Tie, use the Range tool to zoom in the Main Graph. Simply click and drag over the area you want to zoom in to.

Split Tool



Click on a correction object (Note, Line or Curve) with the **Split Tool** to break the object into two separate objects.

Zoom Tool




With the **Zoom tool**, click anywhere in the [Main Graph](#) to zoom in by one step, or hold down Option or Alt while clicking to zoom out one step.

You can also click and drag with the Zoom Tool to select a specific area to zoom in to.

Note: Even if you don't have the Zoom Tool selected, you can still zoom in and out on the Main Graph with the +/- buttons near the scrollbars or with the following modifier key + scrolling techniques:

- Press and hold the Option/Alt key while scrolling up or down with your mouse wheel or trackpad to zoom vertically.
- Press and hold the Command/Control key while scrolling up or down with your mouse wheel or trackpad to zoom horizontally.
- Press and hold both modifier keys at the same time to zoom vertically and horizontally at the same time.
- On Mac trackpads, use the "pinch to zoom" function to zoom in and out.

Hand Tool



Drag the **Hand Tool** in any direction on the [Main Graph](#) to move the area that is displayed.

If you move the cursor with any selected tool into the keyboard area on the left side of the screen, it will temporarily change to the Scroll tool, allowing you to quickly scroll the graph up or down.

You can also scroll up and down on the Main Graph (even when you're not using the Hand Tool) using the scroll wheel on your mouse, or by scrolling left or right on a trackpad.


You can quickly swap to the Hand Tool using the following **keyboard shortcut**:

- Command + Shift (Mac)
- Ctrl + Shift (Windows)

Note: This is a "clutch" type keyboard shortcut, meaning that you will only be swapped to the Hand Tool for as long as you hold down the modifier keys. After you let go of the keys, you will swap back to the tool you were using before.

This shortcut will save you time while working in Graph Mode because it helps minimize the amount of time you'll spend swapping between editing tools.

Nudge




The **Nudge** buttons allow you to move all currently selected correction objects up or down in precise one-cent increments.

This tool is useful for making micro-adjustments to fine tune a Note Object. You can also hold down the Nudge buttons to adjust the selected correction objects up or down a further distance.

The Nudge buttons can be mapped to number keys on your keyboard in the [Key Bindings](#) Preferences Menu for easy access.

Time Correction Tools




In order to use the **Time Correction Tools**, you must first track some audio into Graph Mode using the [Track Pitch & Time](#) function, or open an ARA2 instance of Auto-Tune Pro 11.

The **Point** and **Region** tools are only active where audio has been tracked using Pitch & Time.

For more information on Time Correction, see the [Time Correction Overview](#) and the [Tutorials](#) section.


Point Tool




The **Point** Tool allows you to select a range of audio and then move a point within that range forward or backward in time, compressing and expanding the audio around it.

Using the Move Point Tool is a two step process:


1. Click and drag to select the audio range you wish to operate on. This will highlight the area in blue.



2. Click and drag anywhere within the selected region to move a point forward or backward in time.




Region Tool




The **Region** Tool allows you to select a range of audio, then move a region within that range forward or backward in time, compressing and expanding the audio around it, but leaving the internal timing of the moved region unchanged.

Follow the steps below to use the Region Tool:


1. Click and drag to select the audio range you wish to operate on. This will highlight the region in light blue.
2. Click and drag to select the specific region within that range that you wish to move. This will highlight the region in dark blue.



3. Click and drag anywhere within the dark blue area to move the region in time.
 - a. **Note:** Please keep the maximum [time shifting limit](#) in mind while making adjustments. You will see an error message to let you know when the time compression limit has been reached.



Info Bar



The **Info Bar** gives you realtime information about the correction objects in the Main Graph, depending on where the playhead and cursor are located at any given time.

The **Detected**, **Object**, and **Output** readouts display pitch data wherever the cursor is on the Main Graph. Use these readouts in tandem to compare incoming pitch data, the amount of pitch correction, and the output pitch.




Click on the Info Icon above the [Waveform Graph](#) to toggle the Info Bar On/Off.

Clock



During playback, the **Clock Display** shows the current time position in Minutes:Seconds, or Bars|Beats, depending on the [Time Display](#) setting.

Cursor



The **Cursor Display** shows the current time position of the cursor in the Main Graph.

This is useful for making precise, time-based edits.

Legend



A color coded legend lives on the far right end of the Info Bar to remind you what each pitch curve color represents.

Detected

Detected C3 -42

The **Detected Display** shows the detected pitch ([red curve](#)) at the current cursor position in the Main Graph. The readout includes:

- The letter name of the pitch
- The octave number
- The offset in cents

Object

Object C3

The **Object Pitch Display** shows the target pitch of the [Correction Object](#) (Curve, Line, or Note) at the current cursor position. The readout includes:

- The letter name of the pitch
- The octave number
- The offset in cents

Output

Output C3 +39

The **Output Display** shows the output pitch ([green curve](#)) at the current cursor position in the Main Graph. The readout includes:

- The letter name of the pitch
- The octave number
- The offset in cents

ARA2: Audio Random Access

Background

What is ARA2?

Audio Random Access (**ARA**) increases the amount of communication possible between a DAW and a plug-in, allowing them to exchange more information, such as audio data, tempo, pitch, and rhythm for an entire song, rather than just at the moment of playback.

The increased amount of information exchange removes the need for audio material to be transferred to and from the plug-in in real time. What this means for you, is that ARA allows a plug-in to be used as a more closely integrated part of the DAW's overall interface.

ARA2 is the latest iteration of Audio Random Access technology.

Compatible DAW's


ARA2 instances of Auto-Tune Pro 11 are currently compatible with [Studio One](#), [Logic Pro](#), and [Cubase](#).

Please visit our Knowledge Base to learn more about instantiating Auto-Tune Pro 11 as an ARA2 plug-in, and other DAW-specific ARA considerations.

As a good rule of thumb, please ensure that ARA instances of Auto-Tune Pro 11 are the first plug-ins in your signal chain.

ARA2 Features

Time Ruler




In ARA2 instances of Auto-Tune Pro 11, the Time Ruler above the Main Graph reflects the host's time ruler, and helps you with various ARA functions. (Outlined in red in the screenshot above.)

Bi-Directional Synchronization

One of the most convenient features of ARA2 is the bi-directional synchronization between the host and Graph Mode.


In your host program and in Graph Mode, you'll notice a thin vertical line that represents the current playback location at any given time. This is referred to as a "playhead".



When you move the playhead in the host, the Graph Mode playhead will move to the same location. The reverse is also true - when you click on the Graph Mode Time Ruler to move the playhead, the host's playhead will move to the same location.

Similarly, if a piece of audio is relocated in the host, the same piece of audio will move to the new location in Graph Mode.

Looping Points



In ARA2 instances, looping points will be consistent between the host and Graph Mode. Loops are indicated as blue regions on the Time Ruler, pictured above.

For example, if you create a 30 second loop of your track in the host from 0:00 - 0:30, and start playback, the playhead in Graph Mode will loop in the same way that the host does.

It's also possible to set loop points in Graph Mode. To do so, simply click and drag on the blue Time Ruler at the top of the Main Graph to set the boundaries of the loop. When you make a loop in Graph Mode and start playback, the host will loop in the same specified location.

Note: In Logic Pro, it is not possible to readjust the length or delete a loop from the Auto-Tune Pro 11 ARA interface. Please make these changes in the host's time ruler, and re-track your audio with a moment of playback.

ARA2 Workflow Differences


Automatic Data Transfer

After loading an ARA instance of Auto-Tune Pro 11, pitch and time data for the entire track will instantly be available to edit in Graph Mode.

In all ARA2 instances of Auto-Tune Pro 11, tracked audio will include Pitch & Time information.

Note: *In Logic Pro, a moment of playback is necessary to trigger the automatic data transfer to Graph Mode.*

Re-Track Button




In ARA2 instances, the **Re-Track** button takes the place of the [Track Pitch](#) and [Track Pitch & Time](#) buttons.

If any edits are made to the audio in the host, including edits to the Input Type, Tracking Knob, or Classic vs. Model toggle, it is necessary to re-track the audio in Graph Mode.

The Re-Track button will flash red when a change in the audio is detected, reminding you to re-track the audio.

Note: *After making a change to the tempo or time signature in the host, please re-track your audio. The Re-Track button will not flash after making those changes.*

Logic Pro: ARA2 Workflow Notes



How to Instantiate

Preface: Logic Pro must be opened in Rosetta on Apple Silicon machines to use Auto-Tune Pro 11 as an ARA2 plug-in*:

1. Locate Logic Pro X in the Applications folder.
2. Right-Click on Logic and select "Get Info".
3. In the Info Window, check the "Open in Rosetta" box.

*Please update Logic Pro to version 10.7.5 or later to ensure proper ARA2 functionality.

Please follow the steps below to insert Auto-Tune Pro 11 as an ARA2 plug-in in Logic Pro:

1. Create a new track
2. Click the 'Audio FX' button to open your list of plug-ins
3. Scroll to *Audio Units > Antares > Auto-Tune Pro (ARA)*

To trigger the instantaneous data transfer in Logic Pro, a moment of playback is required.

Dependent vs. Independent Copies

This section will cover the unique operations of duplicated ARA regions and parameters in Logic Pro.

Duplicating/Copying Regions:

Duplicated regions created in the following ways do not share data and parameters with the original copy – they are considered *Independent*:

- Copy and pasting a region with **Cmd + C** then **Cmd + V**
- Holding the **Option** key, then dragging a region with your mouse

If you create a duplicate region using the **Loop Tool** in Logic, it will share data and parameters with the original copy – it is considered *Dependent*.

Duplicating/Copying Tracks with Auto-Tune Pro (ARA):

Press **Cmd + D** to duplicate a track containing an ARA instance of Auto-Tune Pro 11, then hold the Option key and drag the region into a new track.

The newly created region will use separate data and parameters of the original region – it is considered *Independent*.

Notes:

- *Regardless of independence/dependence, every new ARA instance will initialize with the same parameters and data as the original from which it was duplicated.*
- *In Logic, all data transfers occur after a moment of playback. You will not see any changes in data or parameters on a new region until you run the transport.*
- *Track Freezing is not supported on tracks containing an ARA2 instance of Auto-Tune Pro 11.*
- *Time stretching is not supported on tracks containing an ARA2 instance of Auto-Tune Pro 11.*

For more information about Auto-Tune Pro 11's ARA implementation in Logic Pro, please visit the Antares Knowledge Base [here](#).

Studio One: ARA2 Workflow Notes

How to Instantiate

To load an ARA instance of Auto-Tune Pro 11, you must add it as an “Event FX” insert on a specific audio event. To do this, click and drag the VST3 version of Auto-Tune Pro 11 from Studio One’s “Effects” menu onto an audio event.

Auto-Tune Pro 11 will now open up as an ARA2 plug-in, and your audio data will be automatically tracked into Graph Mode.

Dependent vs. Independent Copies

This section will cover the unique operations of duplicated ARA regions and parameters in Studio One.

Duplicating/Copying Events:

Duplicated events created in the following ways share data and parameters with the original copy – they are considered *Independent*:

- Copy and pasting an event with **Cmd + C**, then **Cmd + V**
- Holding the **Option** key, then dragging an event with your mouse
- Pressing **D**


Duplicating/Copying Tracks with Auto-Tune Pro (ARA):

Duplicate Track : Does not duplicate events, so no ARA instances will be duplicated

Duplicate Complete: Duplicates track and events within it. Events duplicated this way will share data.

Separate Shared: By right-clicking an ARA event and selecting ‘separate shared’ this event will use **separate** data and no longer share data / parameters with its original.

Notice the small numbers in the bottom left of each region, pictured below:



Regions with the same number in this position will **share** the same data / parameters. Regions with different numbers will use **separate** data / parameters.

Notes:

- *Regardless of independence/dependence, every new instance should initialize with the same parameters and data as the original from which it was duplicated.*
- *The [Multi-View Instance List](#) will display ARA2 instances in the order they were instantiated, not in chronological order relative to the host's timeline.*
 - *Click on an event on the timeline to jump to that event's instance of Auto-Tune Pro 11.*

For more information about Auto-Tune Pro 11's ARA implementation in Studio One, please visit the Antares Knowledge Base [here](#).

Cubase: ARA2 Workflow Notes


How to Instantiate

When using ARA in Cubase, Auto-Tune Pro 11 will be instantiated directly onto an audio event instead of on the channel strip. To do this, please follow the steps below:


1. Click on the desired audio event with the Object Selection tool:



2. On the Info Line, click Extension:



3. Select Auto-Tune Pro from the dropdown list:



After opening Auto-Tune Pro as an ARA plug-in, all of the audio data from the selected event will be transferred to the plug-in instantaneously.

Dependent vs. Independent Copies

This section will cover the unique operations of duplicated ARA events in Cubase.

Duplicating/Copying Events:

Duplicated events will be considered *Dependent* by default in Cubase, meaning they will share data and parameters with the original copy.

Duplicated events created in the following ways do not share data and parameters with the original copy – they are considered *Independent*:

- Duplicating an event with **Control/Command + D**
- Clicking and dragging an event with your mouse
- Control/Command + Click a dependent event, and select “Convert to Real Copy”
 - This can also be achieved via *Edit > Functions > Convert to Real Copy*

Duplicating/Copying Tracks with Auto-Tune Pro (ARA):

To duplicate a track containing an ARA instance of Auto-Tune Pro 11, right click on the track, then click ‘Duplicate Track’.

The newly created track will use separate data and parameters of the original region – it is considered *Independent*.

Notes:

- *Regardless of independence/dependence, every new ARA instance will initialize with the same parameters and data as the original from which it was duplicated.*

- *The [Multi-View Instance List](#) will display ARA2 instances in the order they were instantiated, not in chronological order relative to the host's timeline.*
 - *Click on an event on the timeline to jump to that event's instance of Auto-Tune Pro 11.*


For more information about Auto-Tune Pro 11's ARA implementation in Cubase, please visit the Antares Knowledge Base [here](#).

Quick Settings and Preferences

The **Quick Settings Menu** and **Preferences Window** allow you to customize the behavior and appearance of Auto-Tune Pro 11 in a variety of ways. The Preferences Window is accessed via the Quick Settings Menu.

To quickly change a setting just for the one instance of Auto-Tune Pro 11, change it in the Quick Settings Menu. To change the default setting of that item, change it in the Preferences Window, then click 'Save As Default'.

Quick Settings



When you click on the Gear Icon, you'll be brought to the **Quick Settings** Menu.

This dropdown menu contains a collection of settings that you may want to edit more frequently than the ones contained in the Preferences Window.

Preferences...

Open the [Preferences](#) Window.

View Tooltips

Click to enable **Tooltips**.

When this setting is enabled, hover over any parameter in the user interface to read a short description of the control and an example use case.

Note: *This setting is persistent across all instances of Auto-Tune Pro.*

View Help Topics

Click to open the Auto-Tune Pro 11 [Help Page](#) in your web browser. This article contains tutorial videos, answers frequently asked questions, and will direct you to other relevant articles in the Antares Knowledge Base.

Reset Window Size


The Auto-Tune Pro 11 plug-in window is completely resizable, and stays sharp at any size. Click and drag the plug-in window to resize it to your liking.

Use this setting to reset the window size back to its default size.

Reset Warning Dialogs

If you previously marked any warning dialogs in Auto-Tune Pro as “Don’t show again”, you can use the **Reset Warning Dialogs** setting to restore them.


For example, if you haven’t used Graph Mode in a while, and need a refresher, you may want to refer to the walkthrough pop-up:



Use Low Latency

If you plan to use Auto-Tune Pro 11 in a live performance or monitor through it in real time while recording, turn on **Use Low Latency** to minimize processing delay.

Move Data Folder




To enable non-destructive time correction editing, Auto-Tune Pro 11 creates a copy of any audio that you track into graph mode using the [Track Pitch & Time](#) function.

Unlike the pitch data generated by the traditional Track Pitch function, which is always stored with the instances of Auto-Tune in your session, the audio recorded for time shifting by the Track Pitch & Time function is saved as one or more separate files elsewhere on your computer.

To help manage the recorded audio data required for time shifting, the **Move Data Folder** setting opens a dialog box that allows you to establish or move the location of the data files.


Rename Data Folder



The **Rename Data Folder** setting serves a similar purpose to the Move Data Folder setting.

It opens a dialog box that allows you to rename the folder where the audio recorded for time shifting by the Track Pitch & Time function is stored.

Show in Graph Mode



The **Show in Graph Mode** sub-menu contains 4 items that can be shown or hidden while working in Graph Mode.

Waveform in Main Graph

Turn this setting on to display the waveform of any tracked audio in the [Main Graph](#), in addition to pitch [curves](#) and pitch [correction objects](#).

Waveform Graph

When this is checked, the [Waveform Graph](#) will be visible in Graph Mode when opening new instances of Auto-Tune Pro 11.

The Waveform Graph can also be shown and hidden by clicking the Waveform Graph icon in the lower right corner of the Main Graph. If you prefer to have a little more room


in the [Main Graph](#), and only reference the Waveform Graph occasionally, you may want to uncheck this setting.

Tracked MIDI

Auto-Tune Pro 11 allows you to record MIDI input in Graph Mode and use the recorded MIDI notes to create Note correction objects. When **Show Tracked MIDI** is on, any recorded MIDI data will be displayed in the Main Graph.

Pitch Lanes


The [Main Graph](#) default mode displays lanes that extend from the left-hand “keys” and are tinted to differentiate the sharps and/or flats. Note objects will snap neatly into these lanes when they are created or adjusted with the [Multi Tool](#).




Note: *Show Pitch Lanes* is only available for Chromatic, Major, and Minor scales.

When Show **Pitch Lanes** is turned off, horizontal **Pitch Lines** are displayed instead.

Pitch Lines represent the center of each pitch on the keyboard, and are useful while working with Lines and Curves. For example, if you're adjusting a green output pitch curve, you can use the pitch lines to ensure that it lines up with the center of the note's pitch.



Graph Mode Settings



The **Graph Mode Settings** sub-menu gives you quick access to a selection of controls that you may want to edit more often than those listed in the Preferences Menu.

The options listed in this menu affect how various Graph Mode functions operate.

Auto Scroll

When **Auto Scroll** is on, the [Main Graph](#) in Graph Mode will automatically scroll during playback to match the playback position of the host application.

You can choose between [Continuous](#) scrolling and [Page-by-Page](#) scrolling in the Graph Mode Preferences.

Snap to Note

The Snap to Note setting allows you to perfectly align [Correction Objects](#) to the pitch grid defined by the current scale setting in Graph Mode.

When moving [Note](#) Objects with the [Multi Tool](#) while Snap to Note is on, they will snap to the nearest scale tone. When using the [Line Tool](#) while Snap to Note is on, any new line segments that you draw will snap to the closest scale note.

Holding down the Shift key on your keyboard while editing will temporarily toggle the state of Snap to Note to its other state.

For example:

- If Snap to Note is *on*, you can hold down Shift to move a Note Object freely between scale notes.
- If Snap to Note is *off*, you can hold down Shift while moving a Note Object to make it snap to the closest scale note.

Play Tone When Moving Notes

When this setting is on, clicking and holding on a Note Object will result in a tone sounding at the current pitch of the Note Object. When you drag the Note Object up or down, you'll hear the tone change to match the position of the Note.

This is useful for hearing when you've reached the target pitch without having to start playback.

Time Display

When **Time Ruler Display** is set to Minutes/Seconds it will display the absolute time in hours, minutes, seconds, and fractions of seconds from the beginning of the timeline.

When set to Bars|Beats, the Time Ruler will display time using bars and beats (as defined by your DAW's tempo).

Enable Time Correction Edits

The **Enable Time Correction Edits** setting enables or disables the [Time Correction](#) features. Unchecking this setting will not delete any time correction edits that you have made- it will only temporarily disable them.

This is useful if you want to compare the timing of the original audio to the time corrected version, without disrupting any pitch correction edits that you may have made.

Version Number

This section will let you know which version of Auto-Tune Pro 11 you're currently using. You can always find and download the latest version of Auto-Tune Pro 11 by opening [Auto-Tune Central](#).

Preferences Window: Introduction

The **Preferences Window** is where you can customize Auto-Tune Pro 11 to your unique workflow. All of the preferences are organized into tabs at the top of the Preferences Window to help you find what you're looking for:

- [General Preferences](#)
- [Graph Mode Preferences](#)
- [Key Binding Preferences](#)

To save your preferences as default for all instances of Auto-Tune Pro 11, turn on **Save as Default**, then click 'Save'.

If you want to make a temporary change to the preferences just for this instance (without overwriting your default preferences) uncheck the Save as Default option before clicking 'Save'.

General Preferences

General	Graph Mode	Key Bindings
Non-ARA Opens Showing:	<input checked="" type="radio"/> Auto	<input type="radio"/> Graph
Appearance:	Dark	▼
Auto Key Detection:	<input checked="" type="checkbox"/>	
Knob Control:	<input type="radio"/> Circular	<input checked="" type="radio"/> Linear
Detune Display:	<input checked="" type="radio"/> Hertz	<input type="radio"/> Cents
Pitch Reference:	<input checked="" type="radio"/> Left	<input type="radio"/> Right
Scales:	<input checked="" type="radio"/> Modern	<input type="radio"/> Legacy
Use OpenGL Graphics:	<input type="checkbox"/>	
MIDI Input Channel:	Off	▼
<input checked="" type="radio"/> Save as Default		Cancel Save

The **General Preferences** allow you to customize your overall experience with Auto-Tune Pro 11. You can change the appearance of the GUI, and choose your preferred mode to open automatically in non-ARA instances, among other options.

Non-ARA Opens Showing

This preference controls the opening behavior for non-ARA instances of Auto-Tune Pro.

When 'Auto' is selected, non-ARA instances of Auto-Tune Pro will open in Auto Mode. Similarly, when 'Graph' is selected, non-ARA instances will open in Graph Mode.

Note: All ARA instances of Auto-Tune Pro will open in Graph Mode by default.

Appearance

Appearance determines the theme of the Auto-Tune Pro 11 GUI. Options include:

- Light
- Dark
- System

If 'System' is selected, Auto-Tune Pro 11 will follow the Appearance settings of your Mac or PC.

Auto-Key Detection

This setting enables Auto-Tune Pro 11 to receive key and scale information from [Auto-Key](#). You may also quickly toggle this setting On or Off using the [Auto-Key](#) button in the Global Controls toolbar.

Auto-Key is also available as a free application on mobile devices to detect and send key and scale information to Auto-Tune Pro 11. [Auto-Key Mobile](#) brings perfect pitch to your pocket!

Knob Control

The **Knob Control** preference lets you choose how you interact with knobs to make adjustments.

- Circular: Click and drag clockwise or counterclockwise to adjust the knob in the respective direction
- Linear: Click and drag up or to the right to turn it clockwise, down or left to turn it counterclockwise

Detune Display

The [Detune](#) function is used to tune to a reference frequency other than the standard A = 440Hz. The **Detune Display** preference lets you choose whether the offset is displayed in cents or Hz.

This is useful when working with an instrument or track that uses a different reference pitch.

Pitch Reference

Auto-Tune Pro 11 can apply pitch correction to stereo tracks while maintaining phase coherence between the two channels. The **Pitch Reference** setting lets you choose which of the stereo tracks will be used to analyze the pitch.

If one channel is cleaner or better isolated than the other, select that channel as the pitch reference.

When using Auto-Tune Pro 11 on a stereo track, both channels should feature the same source material (e.g. a single vocal performance, recorded in stereo using two microphones).

Scales

The **Scales** setting lets you choose which set of scales are available in the [Scale](#) dropdown menu in the Global Controls section of Auto-Tune Pro.

There are two sets of scales available– *Modern* and *Legacy*. The *Modern* scales are those that are commonly found in Western musical styles:

- Chromatic
- Major
- Minor
- Harmonic Minor
- Jazz Melodic Minor
- Dorian
- Phrygian
- Lydian
- Mixolydian
- Locrian
- Major Pentatonic
- Minor Pentatonic
- Blues
- Whole Tone
- Diminished

The *Legacy* selection of scales were present in Auto-Tune Pro X and earlier. These scales are generally considered to be more niche, including options such as Ling Lun, Just, Pythagorean, Arabic, and Indian.

Use OpenGL Graphics

Auto-Tune Pro 11 uses **OpenGL** for improved graphics on computers with compatible graphics card hardware.


To improve performance, OpenGL is disabled by default on Mac. On Windows, OpenGL is enabled by default.

OpenGL can be toggled On/Off on either platform at any time.

MIDI Input Channel

Select the MIDI Channel to receive MIDI Continuous Controller messages.

Graph Mode Preferences



The **Graph Mode Preferences** help you customize your experience while working in Graph Mode. You can toggle waveform and pitch information on/off, choose the type of correction object to create after tracking, and much more.

After Tracking

The **After Tracking** preference lets you choose which type of correction object is automatically created after tracking audio. Options include:

- *Make Note Objects*
- *Make Curves*
- *Import Settings from Auto Mode*
- *Do Nothing*

Zoom After Tracking

The **Zoom After Tracking** setting allows you to customize the zoom behavior on the Main Graph after tracking data into Graph Mode. This preference applies after correction objects are auto-generated and after tracking is ended manually.

When **Zoom To Latest Tracked Data** is selected, the Zoom Range will be adjusted to a level that displays all of the data that was tracked most recently.

If **Zoom To All Data** is selected, the Main Graph will zoom out to a sufficient level that shows all session data present in the graph.

Lastly, if **Do Not Zoom** is selected, the Zoom Range will not be adjusted after tracking data into Graph Mode.

Play Tone When Moving Note Objects

When this setting is on, clicking and holding on a [Note](#) Object will result in a tone sounding at the current pitch of the Note Object. When you drag the Note Object up or down you'll hear the tone change to match the pitch of the Note Object.

Time Ruler Displays

When the **Time Ruler Display** is set to Minutes/Seconds it will display the absolute time in hours, minutes, seconds, and fractions of seconds from the beginning of the timeline.

When set to Bars|Beats, the Time Ruler will display time using bars and beats (as defined by your host's tempo).

Show Waveform in Main Graph


Turn this setting on to display the waveform of any tracked audio in the [Main Graph](#), in addition to pitch [curves](#) and pitch [correction objects](#).

Show Waveform in Note Objects

Turn this setting on to display a waveform of tracked audio within Note Objects. This setting is useful for keeping track of where Note Objects exist in the Main Graph relative to the source audio's waveform.

Show Waveform Graph

When this is checked and saved as default, the [Waveform Graph](#) will be visible in Graph Mode when opening new instances of Auto-Tune Pro 11.



The Waveform Graph can also be shown and hidden by clicking the Waveform Graph icon in the lower right corner of the [Main Graph](#).

If you prefer to have a little more room in the Main Graph, and only reference the Waveform Graph occasionally, you may want to uncheck this.

Waveform Graph Shows

This setting affects the waveform displayed in the [Waveform Graph](#). You can choose to display a single waveform or a dual waveform.

If you select **Single Waveform**, the waveform displayed will reflect tracked audio, as well as any time edits applied to it.

Select **Dual Waveform** to display two adjacent waveforms in the Waveform Graph. The top waveform represents tracked audio and any time edits applied to it. The bottom waveform shows the original 'source' tracked audio, without reflecting any time edits.

The Dual Waveform option is helpful for comparing the original and time-edited audio side by side.



Show Input Pitch Curves

Turn this setting on to display the [Red Input Pitch Curves](#) in Graph Mode. When disabled, only the various [Correction Objects](#) (Line, Curve or Note) will be visible.

Show Output Pitch Curves

Turn this setting on to show the [Green Output Pitch Curves](#) in Graph Mode. When disabled, only the various [Correction Objects](#) (Line, Curve or Note) will be visible.

Display Vertical Line at Cursor Position

Turn this setting on to show a vertical line in the [Main Graph](#) to indicate the position of the cursor.

Scroll Graph

When [Auto Scroll](#) is on and set to **Continuous** Scrolling, the [Main Graph](#) in Graph Mode will continuously follow the playback position of the host application.

With **Page-by-Page** scrolling, the display remains stationary until the play position reaches the right-hand edge of the window, at which time the display jumps to the next screen of data.

When Auto Scroll is off, the [Main Graph](#) display will remain where you leave it, and will not scroll automatically.


Vertical Scrolling

This setting allows you to customize the behavior of vertical scrolling when using the mouse wheel or trackpad.

- The **Traditional** setting works as follows:
 - When you scroll down, note objects move up in the graph, and the scrollbar indicator moves down.
 - This setting is selected by default.
- The **Natural** setting works as follows:
 - When you scroll down, note objects move down in the graph, and the scrollbar indicator moves up.

Use Custom Cursors For Editing Tools

Turn this setting on to display different cursor shapes in the Main Graph to help you select ranges and grab and drag objects (e.g., the object cursor, the anchor point cursor, etc.). All custom cursors are displayed in context in the screenshot below:



Note: Some host applications mistakenly think that they own the cursor when it is in a plug-in window. This may cause the cursor to flash as the host and Auto-Tune Pro 11 alternately try to set the cursor shape. If this is bothersome, turn off Custom Cursors.

Disable Cursors While Playing

Check this box to disable the custom cursors in Graph Mode only when the transport is running.

Show Note Labels On

This setting allows you to choose between showing all notes on the graph mode keyboard or just on the root notes.

With the **All Keys** choice, note labels will be displayed on all keyboard keys.

With the **Root Note Keys Only** choice, note labels are displayed on only the root note of the currently selected key.

Default Retune Speed For

Sets the default [Retune Speed](#) that will be assigned to [Correction Objects](#) (lines, curves , and Note Objects) when they are first created.

You can also change the Retune Speed of any correction objects in Graph Mode by selecting the object or objects and adjusting the Retune Speed control.

Key Binding Preferences

General	Graph Mode	Key Bindings	
Use the drop-down menus to map Auto-Tune Pro functions to the 0-9 keys at the top of your keyboard. When working in graph mode, press the assigned key to execute the assigned function.			
1:	Tool: Draw Lines	6:	Tool: Zoom
2:	Tool: Draw Curves	7:	Tool: Range
3:	Tool: Draw Notes	8:	Tool: Hand Scroll
4:	Tool: Multi	9:	Tool: Move Point
5:	Tool: Split	0:	Tool: Move Region

Save as Default

The **Key Binding Preferences** allow you to assign your most commonly used Graph Mode tools and controls to the row of number keys at the top of your keyboard. Click on the dropdown menu for each key to reveal several dozen functions to choose from.

The default key bindings on keys 1-0 correspond to the editing tools in Graph Mode, in the same order they appear on the toolbar.

Tutorials

The following tutorials will help you master a variety of features and workflows in Auto-Tune Pro 11. To best demonstrate the workflows described in these tutorials, we recommend opening the Graph Mode Preferences menu, and changing the following default settings:

- Set [After Tracking](#) to “Do Nothing”
- Enable [Show Input Pitch Curves](#)
- Enable [Show Output Pitch Curves](#)

Before diving into the tutorials, please visit the [Legacy Installers Page](#) on our website, and select “Auto-Tune Pro 10.0” from the dropdown menu to download the necessary Tutorial Files.

... AUTO-TUNE

Auto-Tune Unlimited Auto-Tune Editions Vocal Effects Learning Center Special Offers Support **FREE TRIAL** ENG > Sign In

Discontinued Software Downloads

Download the final versions of previously discontinued plug-ins, as well as the discontinued 32-bit-only versions of our current 64-bit compatible plug-ins.

Note: These installers are for people who already own a license for these products. If you're looking for a free trial version, please see our [Product Demos](#) page.

Auto-Tune 10.0

Auto-Tune 10.0

Mac

Auto-Tune Pro (AAX, AU, VST3) - 10.0 (255 MB)

Auto-Tune Pro Tutorial Files (45 MB)

PC

Auto-Tune Pro (AAX, VST3) - 10.0 (226 MB)

Auto-Tune Pro Tutorial Files (45 MB)

Click Here

Feedback

The Auto-Tune Effect

In addition to being the worldwide standard in professional pitch correction, Auto-Tune is the tool of choice for one of the signature vocal sounds of popular music: the **Auto-Tune Effect**.

First heard on Cher's 1998 hit song "[Believe](#)," variations of the Auto-Tune Effect have appeared in songs from a huge variety of artists. Since there seems to be a lot of mythology about how it's accomplished, we thought we'd provide the official Antares version here.

What is it?

The Auto-Tune Effect is what is technically known as "pitch quantization." Instead of allowing all of the small variations in pitch and the gradual transitions between notes that are a normal part of singing, the Auto-Tune Effect limits each note to its exact target pitch, stripping out any variation, and forcing instantaneous transitions between notes.

How To Recreate It

There are three key elements to producing the Auto-Tune Effect in Auto-Tune Pro 11:

1. Set [Flex-Tune](#) to 0.
2. Set [Retune Speed](#) to 0.
3. Pick the [Key](#) and [Scale](#) of your track.

That's all you need to recreate the Auto-Tune Effect, but there are some possible variations in approach, depending on whether you want to use [Auto Mode](#) or [Graph Mode](#). See below for more details:

Auto Mode

1. Set [Flex-Tune](#) and [Retune Speed](#) to 0.
2. Select the [Key](#) and [Scale](#) of your track.
3. Play your track. If you like the result, you're done!


4. If you're not happy with the result, try making one or more of the following adjustments:
 - Edit the scale notes using the [Keyboard](#) or [Scale Controls](#). Adding or removing scale notes can give you distinctly different effects. Removing some notes can be especially effective for a more dramatic effect on note transitions.
 - Try a different key and/or scale.
 - Try a Retune Speed of 2, 3 or a bit slower. This will allow slight pitch variations and more gradual note transitions, but may result in the right effect for a particular performance.
 - Try turning on [Classic Mode](#), for a subtle variation of the Auto-Tune Effect.
 - Don't forget your host application's bypass and automation functions. Limiting the Auto-Tune Effect just to specific phrases can provide sonic contrast in your song.

Graph Mode

[Note](#) Objects in Graph Mode will give you more detailed control over the Auto-Tune Effect.

1. We want to start by quantizing all of our Note Objects. Open the Graph Mode Preferences Window, and set the default Retune Speed on Note Objects to 0.
 - a. Alternatively, you can select existing Note Objects with the Multi Tool or Range Tool, and manually change their Retune Speed to 0.
2. Click the [Track Pitch](#) button and begin playback to track your audio into Graph Mode.
 - a. Alternatively, open Auto-Tune Pro 11 as an [ARA2](#) plug-in to track audio automatically.
3. Click the [Create Notes](#) button.

- a. If necessary, adjust the [Density](#) control to get as accurate a representation of the desired target notes as possible.
4. Make sure that all of the Note Objects in the range where you want the effect line up with each other (this will ensure that all of the note transitions are instantaneous).
 - a. If the Note Objects don't line up, either use the [Multi Tool](#) to extend existing Note boundaries so that they do, or use the [Note Tool](#) to draw new notes to fill in any gaps.
 - b. The [Display Vertical Line at Cursor Position](#) preference is helpful in ensuring there aren't any gaps between Note Objects.



5. Play your track. If you like the result, you're done!
 - a. If you're not happy with the result, experiment with changing the pitch or length of individual notes. The beauty of Note Objects is that you can literally sculpt any melodic contour to get exactly the effect you desire.

Auto Mode Basics

This tutorial will guide you through the basic Auto Mode functions using the “A2- A3-A2 sweep,” tutorial file.

This is a simple synthesized waveform sweeping slowly from A2 up to A3 and back to A2. While it is unlikely that you’d ever need to process such an input with Auto-Tune Pro 11, it provides a very clear example of how the main Auto Mode controls work.

To Begin

1. Load or import “A2-A3-A2 sweep” into a track of your DAW. Play the track to hear the unprocessed audio.
2. Open Auto-Tune Pro 11 as an insert effect on that track.

Scale and Key Settings

3. Set the [Key](#) to “A” and the [Scale](#) to “Major.”
4. Set [Retune Speed](#) to 0.
5. Set [Flex-Tune](#) to 0.
6. Set “A2-A3-A2 sweep” to loop continuously in your DAW and start playback.

What you will hear is an A major scale. This is because Auto-Tune is continuously comparing the input pitch to the notes of the A major scale and instantly correcting the output pitch to the nearest of the scale tones.

Remove Notes

1. Open [Advanced View](#).
2. In the [Scale Controls](#) tab, click the [Remove](#) buttons under the notes D, F#, G# and B.



3. Play "A2-A3-A2 sweep" again.

You will now hear an arpeggiated A Major triad because you have removed all the other notes from the scale.

Bypass Notes

1. In the [Scale Controls](#) tab, [Bypass](#) the note E.
2. Play "A2-A3-A2 sweep" again.

You'll now hear the effect of bypassing the E. When the input pitch approaches E, Auto-Tune passes the input through uncorrected.

Retune Speed

1. Set the [Retune Speed](#) to 0.
2. Play "A2-A3-A2 sweep."
3. Set the Retune Speed to 30.
4. Play "A2-A3-A2 sweep" again. Compare the 30 setting to the 0 setting.
5. Experiment with other Retune Speed settings.

The setting of 0 (milliseconds) is fast, and Auto-Tune Pro 11 makes instantaneous pitch changes. The setting of 30 is slower, which means the pitch changes will be more gradual.

In short, Retune Speed determines how rapidly pitch correction is applied to the incoming pitch.


Detune

1. Set the [Retune Speed](#) to 0.
2. In the [Scale Controls](#) tab, click the [Remove](#) buttons below all the notes except F#.
3. Play “A2-A3-A2 sweep” again. As the sound is playing, move the [Detune](#) knob.

The output pitch will be locked to F#, but you’ll hear the output pitch change with the Detune knob movement. This is because the Detune knob is changing the pitch standard of the scale.

Create Vibrato

1. In the [Vibrato Controls](#) tab, Select Sine Wave from the [Shape](#) menu in the [Create Vibrato](#) section.
2. Play “A2-A3-A2 sweep” again.
3. Experiment with the other Create Vibrato controls to hear their effects.



Flex-Tune

This tutorial will guide you through the use of [Flex-Tune](#) using the “A2-A3-A2 sweep” tutorial file.

To begin

1. Load or import “A2-A3-A2 sweep” into a track of your DAW.
2. Set up Auto-Tune Pro 11 to be an insert effect on that track.
3. Set the [Key](#) to A and the [Scale](#) to Major.
4. Set the [Retune Speed](#) to 0.

No Flex-Tune

1. Set [Flex-Tune](#) to 0.
2. In the [Scale Controls](#) tab, click the [Remove](#) buttons next to the notes D, F#, G#, and B.



3. Play “A2-A3-A2 sweep.”

You’ll hear an arpeggiated A Major triad because you have removed all the other notes from the scale.

Some Flex-Tune

1. Set [Flex-Tune](#) of 10.
2. Play “A2-A3-A2 sweep” again.

With a lower Flex-Tune setting such as 10, the correction range around each scale note is still quite wide. You will hear each note of the A Major triad instantly tuned as the sweep enters the correction range, but as the sweep moves out of the correction range, you will hear it transition to the next note without correction.

More Flex-Tune

1. Set Flex-Tune to 55.
2. Play “A2-A3-A2 sweep” again.

At higher Flex-Tune settings, the correction range around each scale note becomes more narrow. Consequently, each scale note will be tuned to only briefly as the sweep passes through the narrow correction range and will transition to the next note without correction as it leaves the correction range.

Ignore Vibrato

This tutorial will demonstrate the [Ignore Vibrato](#) function. This feature helps Auto-Tune identify pitches correctly when a performance includes vibrato so wide that it approaches adjacent notes.

Auto Mode

1. Load “wide_vibrato” into a track of your DAW.
 - a. This is a recording of a male voice singing a sustained G with a wide vibrato.
2. Play the track to hear the unprocessed audio. In addition to the vibrato, you’ll notice that the singer drifts alternately sharp and flat.
3. Set up Auto-Tune Pro 11 to be an insert effect on that track.
4. Set the [Key](#) to C and the [Scale](#) to Chromatic.
5. Set the [Input Type](#) to *Low Male*.
6. Set [Retune Speed](#) to 24.
7. Set “wide_vibrato” to loop continuously in the host application and begin playback. Watch the blue detected pitch indication on the [Keyboard](#), and listen to the result. As you will hear, whenever Auto-Tune thinks G# or F# is the target pitch, it will move the input closer to those notes, instead of toward G.
8. Open [Advanced View](#) to show the [Scale Controls](#), then click [Ignore Vibrato](#) to turn it on. With Ignores Vibrato engaged, Auto-Tune recognizes the pitch deviations as vibrato and continues to use G as the target pitch.

Graph Mode (with Create Curves from Auto Mode)

For the purposes of this tutorial, please set the [After Tracking](#) preference to “Do Nothing”.

1. Still using “wide_vibrato,” set up the parameters in Auto Mode as described in Steps 1-5 above.
2. In Auto Mode, set [Retune Speed](#) to 0.
3. In the [Scale Controls](#) tab, make sure Ignores Vibrato is *Off*.
4. Set Auto-Tune Pro 11 to Graph Mode.
5. Click the [Track Pitch](#) button and begin playback to track the audio into Graph Mode.
 - a. Alternatively, open Auto-Tune Pro 11 as an [ARA2](#) plug-in to track audio automatically.
 - b. If the [Show Input Pitch Curves](#) preference is enabled, a red curve representing the detected pitch contour of the audio will be drawn on the Main Graph.
6. Stop playback, and click the [Create Curves from Auto Mode](#) button.
 - a. A blue curve will appear, which represents the pitch correction that results from processing the audio with the current Auto Mode settings.
 - b. Note all the instances where G# or F# are identified as the target pitch.
7. Switch back to Auto Mode.
8. In the [Scale Controls](#), set [Ignore Vibrato](#) to *On*.
9. Return to Graph Mode.
10. Click the Create Curves from Auto Mode button.
11. Notice that the blue curve is now a straight line on G, indicating that Auto-Tune Pro 11 has correctly identified the pitch deviations as vibrato and has not chosen F# or G# as the target pitch.

Natural Vibrato Function

This tutorial will demonstrate the [Natural Vibrato](#) function using the “wide_vibrato” tutorial file. The Natural Vibrato function allows you to increase or diminish the range of vibrato that is already present in your audio.

1. Load or import “wide_vibrato” into a track of your DAW.
 - a. This is a recording of a male voice singing a sustained G with a wide vibrato. Play the track to hear the unprocessed audio.
2. Open Auto-Tune Pro 11 as an insert effect on that track.
3. In Auto Mode, Set the [Key](#) to C and the [Scale](#) to Chromatic.
4. Set the [Input Type](#) to *Low Male*.
5. Set [Retune Speed](#) to 24.
6. Set “wide_vibrato” to loop continuously and begin playback.
7. Set Natural Vibrato to 12 and note the effect on the vibrato. Set Natural Vibrato to -12 and note the effect on the vibrato.
8. In the [Scale Controls](#) tab, set all Scale notes to [Bypass](#) to disable any pitch correction. Again, adjust the Natural Vibrato control and note that it’s still active even when pitch correction is not being applied.

Transpose and Formant Control

This tutorial will demonstrate the pitch shifting, formant correction, and throat modeling capabilities in Auto-Tune Pro 11. We will use the “hidin_vocal.wav” and “hidin_accomp.wav” tutorial files.

1. Load the audio files onto two tracks in your DAW.
2. Open Auto-Tune Pro 11 as an insert effect on the track with the “hidin_vocal” audio file.
3. In Auto Mode, Select Ab minor as the [Key](#) and [Scale](#), and *Alto/Tenor* as the Input Type.
4. Set the [Retune Speed](#) to 20.
5. Play the audio file.
6. Set the [Transpose](#) control to 7 (a perfect fifth up).
 - a. Check to be sure that [Formant](#) is *Off*.
7. Play the audio file and listen to the quality of the voice. Since the formants are being shifted with the pitch, you will hear the familiar “chipmunk” effect.
8. Click the Formant button to turn on formant correction.
9. Play the audio file again and note the difference.
10. Play the audio file again while adjusting the [Throat Length](#) control to hear the effect of changing the modeled vocal tract.
11. Repeat steps 5 through 9 with different settings of the Transpose control.

Graph Mode Basics


This tutorial will introduce you to the basic Graph Mode functions, using the “A2-A3-A2 sweep” tutorial file.

Track Pitch

1. Load or import “A2-A3-A2 sweep” into a track of your DAW. Play the track to hear the unprocessed audio.
2. Open Auto-Tune Pro 11 as an insert effect on that track.
3. Switch to Graph Mode.
4. Click the [Track Pitch](#) button and begin playback to track the audio into Graph Mode.
 - a. Alternatively, open Auto-Tune Pro 11 as an [ARA2](#) plug-in to track audio automatically.
 - b. If Correction Objects are generated automatically after tracking, set the [Key](#) to A and the [Scale](#) to Major.
 - c. If the [Show Input Pitch Curves](#) preference is enabled, a red curve representing the detected pitch contour of the audio will be drawn on the Main Graph.
5. Stop playback.


Zoom Tool

1. Select the [Zoom Tool](#) and left click around the [red curve](#) to zoom into it.
2. Hold down the Option or Alt key on your keyboard and click on the graph with the Zoom Tool to zoom out one step.
3. Release the Option/Alt key and click on the graph with the Zoom Tool to zoom back in one step.



Line Tool


1. Select the [Line Tool](#) and draw a line similar to the one pictured below (in blue).
 - a. By clicking multiple anchor points on the graph, line segments joining the points will be drawn.
 - b. To erase the last point entered, press Delete on your keyboard.
 - c. When done, double-click the last point or press Esc on your keyboard.
 - d. A green output pitch curve will appear, reflecting the output pitch that results from the default Retune Speed as applied to the Line object.



2. With the Line still selected, set the [Retune Speed](#) to 0 and observe the green output curve. Play back the sound to hear the effect.
3. Experiment with other Retune Speed settings, and note the effect on the green output curve. Play the track again to hear the result of applying different retune speeds to a Line object.

Curve Tool

1. Select the [Curve Tool](#) and create a curve similar to the one shown below.
 - a. Click and hold the mouse button and drag to draw the curve.
 - b. When done, release the mouse button.



2. Play back the sound to hear the effect.
3. Vary the Retune Speed between 0 and 400 and note the effect on both the green output curve and the audio.



Multi Tool

1. Select the [Multi Tool](#).
2. Click and drag the Multi Tool across the Main Graph to select objects.
3. Move the cursor over curves and anchor points.
 - a. Practice selecting entire curves and individual anchor points.

4. Use the Multi Tool to drag selected curves and individual anchor points up and down.
5. Double-click anywhere on a [Line](#) object to create a new anchor point.
6. Use the Multi Tool to drag the new point to a new position.
7. Still using the Multi Tool, double-click on the new anchor point you created to delete it and return the line to its initial state.

Split Tool

1. Select the [Split Tool](#) and click on an existing line or curve to break it in two at that point.
2. Select the [Multi Tool](#), and use it to drag each of the new endpoints to a new position.




Create Curves and the Line Tool

This tutorial will demonstrate two approaches to creating [Correction Objects](#) in Graph Mode: the [Create Curves](#) function and the [Line Tool](#).


Create Curves

The Create Curves function creates new [Curve](#) objects from the detected pitch contour data. The Curve objects can then be dragged and stretched for very precise pitch correction.


1. Load or import the “Crowd All” tutorial file into a track of your DAW.
2. Open Auto-Tune Pro 11 as an insert effect on that track and switch to Graph Mode.
3. Press the [Track Pitch](#) button and begin playback to track the audio into Graph Mode.
4. Select the [Zoom Tool](#) and zoom into the red curve for the last word, “together.”
5. Click and drag with the [Range Tool](#) to select the “-gether” part of the word “together.”




6. Click the [Create Curves](#) Normal button. Auto-Tune Pro 11 will create a new blue curve object from the existing pitch data as well as a green output curve that reflects the default Curve Retune Speed.
 - a. **Note:** The new curves may be difficult to see at first because they may exactly overlay the red curve.



7. Click on the background of the Main Graph with the [Range Tool](#) to deselect the Curve object.
8. Select the [Multi Tool](#) and click precisely on the left end of the long curve to select only the left anchor point. Drag the anchor point straight up, stretching the curve so it is centered around the D3 graph line.



9. Drag the Multi Tool across the last curve to select it. Then move the Multi Tool over the body of a correction curve so that the cursor changes to the horizontal bar. Click and drag the curve so that it's centered on the C3 graph line.




10. Play back the track and listen to the result.

Line Tool

Here is an alternative approach to the same pitch problem using the [Line Tool](#).

1. Click “Select All”, then click “Cut” to delete the curves you created in the steps above.
2. Make sure [Snap To Note](#) is on in the Quick Settings Menu, and use the Line Tool to draw a horizontal line at C3 as shown below.




3. Set the [Retune Speed](#) to 20 and play back the sound. Experiment with other Retune Speeds to see their effect on the green correction curve and to hear their effects.


Create Curves from Auto Mode

The [Create Curves from Auto Mode](#) function lets you display pitch corrections that would result from specific Auto Mode settings, and edit them in Graph Mode.


1. Load or import the “Crowd All” tutorial file into a track of your DAW.
2. In Auto Mode, set the [Key](#) and [Scale](#) to C Major, and the [Retune Speed](#) to 20.
3. Switch to Graph Mode.
4. Press the [Track Pitch](#) button and begin playback to track the audio into Graph Mode.
5. Select the [Zoom Tool](#) and zoom to the red curve for the words “crowd all rushed”.



6. Use the [Range Tool](#) to drag a selection in the [Main Graph](#) or [Waveform Graph](#) as shown:




- Click the [Create Curves from Auto Mode](#) button to create a new blue [Curve](#) object from the existing pitch data as well as a green output curve.




Assuming that this entire phrase should be centered around E3, there are several problem spots where the pitch is being incorrectly adjusted towards neighboring tones.

- Switch to Auto Mode, and open [Advanced View](#). In the [Scale Controls](#) tab, click the Remove buttons next to C, D, F, A, and B.



- Return to the Graph Mode.
- Press the Create Curves from Auto Mode button to create new blue and green curves from the existing pitch data.



Note how the pitch errors from the previous curve have been removed. Also, note the raised pitches indicated above.


This occurs because the Auto Mode Retune slider value of 20 is slow compared to the rapidly increasing pitch that is occurring at that point in time. But even with the raised pitches, the average output pitch is centered on E3 and the phrase sounds in tune.

Create Notes


This tutorial will help you become familiar with the [Create Notes](#) function and how [Note Objects](#) are used for pitch correction and selective pitch shifting.

For this tutorial, we will use the “dont_give_up_vocal.wav” and “dont_give_up_accomp.wav” tutorial files.

1. Load or import the audio files onto two tracks in your DAW.
2. Open Auto-Tune Pro 11 as an insert effect on the vocal track and switch to Graph Mode.
3. Select D Major as the [Key](#) and [Scale](#), and *Soprano* as the [Input Type](#).
4. Press the [Track Pitch](#) button.
 - a. Alternatively, open Auto-Tune Pro 11 as an [ARA2](#) plug-in to track audio automatically.
5. Play the project and track the first 17 seconds of the track (until right after the word “remain”), then stop playback.




6. Click the [Create Notes from Audio](#) button.




7. Start playback.
 - a. Note that the default settings for [Density](#) and Retune Speed do a good job of correcting the pitch for most of the phrase. However, the final syllable of “remains” goes so flat that some additional adjustment is necessary.

The first thing we need to do is correct the dip in pitch before the final C#3. We could do this by selecting each of the two low Note Objects (A2 and B2) and individually moving them up to C#3, but it’s easier to just expand the existing C#3 object.


8. With the [Zoom Tool](#), zoom into the word “remains.”



9. Select the [Multi Tool](#) and move the cursor over the left end of the long C# note, then drag the left end of the note to extend it until it lines up against the end of the previous D3 Note Object.




10. Since there’s also a large dip in pitch towards the very end of the word, move the cursor over the right end of the long C#3 note and drag it to the right until it extends to the end of the phrase.




11. Still with the Multi Tool selected, click on the final C#3 to select it. Now adjust the [Retune Speed](#) for the desired correction (start with a value of 10 or so).
 - a. Note that with a long held note like this, too fast a Retune Speed can sound unnatural. The trick is to select a speed that pulls the attack in tune, while still allowing enough of the singer's original natural variation.

We'll continue with an example of selective pitch shifting.

1. Ensure that [Formant](#) is on.
2. With the [Multi Tool](#) selected, move the cursor over the middle of the C#3 note and drag it up one semitone to D3.
 - a. Play the file and listen to the melodic change.



3. For a melodic variation, select the [Split Tool](#) and click on the now D3 note at the 16.052 second point to cut it into two notes.
 - a. **Note:** Turn on the [Info Bar](#), and use the [Cursor](#) section to help you find this location.
4. Select the Multi Tool again and drag the left half of the note back down to C#3.




5. Play the file and listen to the result.

Time Correction


In this tutorial we'll use the [Point Tool](#) and [Region Tool](#) to correct timing errors in a lead vocal track. You can use the bars and beats scale as a reference for correction, and we've also included a harmony track with proper timing so that you can try correcting by ear.

The Region Tool


1. Load or import the audio files "Time_vocal" and "Time_accomp" into two separate tracks in your DAW, and set the tempo to 110 BPM. Listen to the tracks to become familiar with them.
2. Open Auto-Tune Pro 11 as an insert effect on the "Time_vocal" track and select Alto/Tenor as the [Input Type](#).
3. Switch to Graph Mode, then go to Settings and set the [Time Display](#) to Bars|Beats.
4. Press the [Track Pitch & Time](#) button and begin playback to track the audio.
 - a. Alternatively, open Auto-Tune Pro 11 as an [ARA2](#) plug-in to track audio automatically.
5. Adjust the zoom and scroll controls to focus on the first two bars (there is one bar of silence at the beginning of the tracks).
 - a. Note that the vocalist comes in early with the first word, "Time." Since this word is isolated (i.e., there's silence after it), we'll use the Move Region Tool to move it into its proper place.




6. Use the [Region Tool](#) to select the initial range from the beginning of the third beat of the first measure to the end of the second measure.
 - a. **Note:** *The precise boundaries of this selection are not critical, as long as there are a few beats of silence before and after the note to be moved.*



7. Use the Region tool to select the region to be moved.
 - a. Select the region from the beginning of the breath before the note (at time position 1:3.9) to the end of the note's decay (at time position 2:3.62).



8. Still using the Region tool, click and hold anywhere in the region selected in Step 7 and move the region to the right until the beginning of the note's main attack (the part after the initial breath) is lined up exactly on the first beat of measure 2.




Play back your track and note that the two vocal parts are now perfectly in sync. You can also disable and re-enable Time Correction in the Quick Settings menu to compare the original and time-edited versions.


The Point Tool: Adjusting an Ending

Moving on in the track, we'll use the [Point Tool](#) to correct a phrase that starts at the right point but ends late.


1. Adjust the zoom and scroll controls to focus on bars 3 through 5. Play the track and note that the end of the second phrase (the end of the word "illusion"), is sustained too long.



2. Use the Point Tool to select the range from the beginning of the last syllable of "illusion" (at time position 4:1.80) to the beginning of the breath before the following note (at time position 5:2.23).



3. Use the Point Tool to select the point to be moved.
 - a. In this case we want to move the very end of the phrase while leaving the beginning in place. Place the cursor over the very end of the note (at time position 5:2.10).
 - b. Click and drag to move the end point back to the beginning of measure 5.




Play back the track and note that once again the two vocal parts are now perfectly in sync.


The Point Tool: Adjusting an Internal Syllable

For our final example, we'll use the [Point Tool](#) to correct a syllable in the middle of a word.


1. Adjust the zoom and scroll controls to focus on bars 7 through 9. Play the track and note that the start of the last syllable in the final word of the track ("delusion"), starts slightly too early.



2. Use the Point Tool to select the range from the beginning of the word "delusion" (at time position 7:4.63) to a beat past the end of the track (at time position 9:2.0)



3. In this case we want to move the start of the syllable while leaving the beginning and end of the selected word in place.
 - a. Place the cursor over the beginning of the last syllable (at time position 8:1.73).
 - b. Click and drag to move the end point to the right to time position 8:2.0.




Play back your track and note that once again the two vocal parts are now in sync. You can also disable and re-enable Time Correction in the Quick Settings menu to compare the original and time-edited versions.

Creative Time Editing

In this tutorial we'll use the [Region Tool](#) for a creative, rather than corrective, purpose.

1. Load or import the audio file "Bass_riff" into a track of your DAW, and set the tempo to 110 BPM.
 - a. Listen to the track to become familiar with it.
 - b. We're going to use the Region Tool to move the second note of the pattern and change the feel of the bass line.
2. Open Auto-Tune Pro 11 as an insert effect on the track and select *Bass Instrument* as the [Input Type](#).
3. Switch to Graph Mode, then go to the Quick Settings menu to set the [Time Display](#) to Bars|Beats.
4. Press the [Track Pitch & Time](#) button and begin playback to track the audio into Graph Mode.




5. Adjust the zoom and scroll controls to focus on the first measure of the bass line.
 - a. Our goal will be to move the second note, so that instead of being a pickup note to the third beat, it falls squarely on the second beat, creating a different feel to the line.




6. Use the Region tool to select the initial range from the end of the first note's decay to the end of the second note's decay.



7. Use the Region tool to select the region from the beginning of the second note to a bit before the end of its decay.
 - a. The reason that we don't select the entire note is that when we move it forward in the next step, we want to leave a bit of it for Auto-Tune to stretch into a natural decay leading into the note on the third beat.



8. Still using the Region tool, click and hold anywhere in the region selected in Step 7, and move the region to the left until the beginning of the note is lined up exactly on beat 2.



Play back your track and note the new feel. Also note how the Auto-Tune Pro 11 time shifting algorithm has turned the small bit of audio at the end of the moved note into a natural sounding decay leading into the following C.

Keyboard Shortcuts

General

Keypress	Action	Result
Option/Alt	Click on knob	Reset to default position
Double Click	Double click knob	Reset to default position
Command/Ctrl		Fine tune knob adjustment
Command/Ctrl + Z		Undo
Shift + Command/Ctrl + Z		Redo
	Right Click on Control	Open MIDI Mapping Menu

Auto Mode Keyboard

Keypress	Action	Result
Command/Ctrl	Click any key on the keyboard	Reset keys to default state
Shift		(Clutch) Disable the Latch Keyboard Mode

Graph Mode

Keypress	Action	Result
Command/Ctrl + Shift		(Clutch) Swap to Hand Tool
Command/Ctrl + A		Select All Correction Objects
Command/Ctrl	Click on multiple Correction Objects	Select multiple Correction Objects
Command/Ctrl + X	Click on Correction Object(s) first	Cut (deletes and copies) Correction Objects
Command/Ctrl + C	Click on Correction Object(s) first	Copy Correction Objects
Command/Ctrl + V	Click on Correction Object(s) first	Paste Correction Objects from the internal clipboard
Delete	Click on Correction Object(s) first	Delete Correction Objects
Shift	Drag Note Object	Disable "Snap to Grid" when moving Note Objects
Option/Alt	Click and Drag Correction Object	Allows you to move Correction Objects horizontally
Option/Alt	Click on a Zoom State button	Save your current zoom setting to that Zoom State button
Shift	Scroll	Scroll Horizontally
Command/Ctrl + Option/ Alt	Scroll	Horizontal Zoom In/Out
Option/Alt	Scroll	Vertical Zoom In/Out
R	Scroll	Adjust Per-Object Retune Speed
V	Scroll	Adjust Per-Object Vibrato
F	Scroll	Adjust Per-Object Formant

MIDI Mapping Master List

The following is a list of all controls that can be mapped to MIDI hardware, organized by section.

Global Controls

- Bypass
- Input Type
- Key
- Scale
- Detune
- Formant Correction
- Throat Length
- Transpose
- Wet/Dry Mix

Pitch Correction Controls

- Retune Speed
- Flex-Tune
- Humanize
- Natural Vibrato

Advanced Mode Controls

Vibrato Controls

- Shape
- Rate
- Delay
- Onset Rate
- Vibrato Variation

- Pitch Amount
- Amplitude
- Formant

Scale Controls

- Ignore Vibrato

MIDI Functions

- Learn Scale from MIDI
- Target Notes via MIDI
- MIDI Octaves

Harmony Player Controls

- Bypass Harmonies
- Mixer Mode
- Modern Scale
- Transpose in Scale
- Scale Transpose
- Interval Type
- Pan or Width
- Mute Main Voice
- Naturalize
- Transition Time
- Pitch Variation
- Timing Variation

Harmony Voice Module Controls

- Voice 1 Fixed Interval
- Voice 2 Fixed Interval
- Voice 3 Fixed Interval
- Voice 4 Fixed Interval

- Voice 1 Scale Interval
- Voice 2 Scale Interval
- Voice 3 Scale Interval
- Voice 4 Scale Interval

- Voice 1 Pad Mode
- Voice 2 Pad Mode
- Voice 3 Pad Mode
- Voice 4 Pad Mode
- All Voices Pad Mode

- Voice 1 Gain
- Voice 2 Gain
- Voice 3 Gain
- Voice 4 Gain

- Voice 1 Pan
- Voice 2 Pan
- Voice 3 Pan
- Voice 4 Pan

- Voice 1 Spread
- Voice 2 Spread
- Voice 3 Spread
- Voice 4 Spread

- Voice 1 Formant
- Voice 2 Formant
- Voice 3 Formant
- Voice 4 Formant

- Voice 1 Solo
- Voice 2 Solo
- Voice 3 Solo
- Voice 4 Solo

- Voice 1 Trigger
- Voice 2 Trigger
- Voice 3 Trigger

- Voice 4 Trigger
- All Voices Trigger

Envelope Controls

- Bypass Envelope
- Attack
- Release

Equalizer Controls

- Bypass Filter
- Filter Shape
- HPF Frequency
- HPF Slope
- BPF Frequency
- BPF Q
- BPF Level
- LPF Frequency
- LPF Slope

Gate/Stereo Width Controls

- Bypass Gate
- Side Chain Source
- Gate Threshold
- Stereo Width